

VMS SES

User's Guide

Version 5.3-1

Order Number: QS-970AA-UG

June 1990

This manual introduces Version 5.3-1 of the VMS Security Enhancement Service to the general user. In addition, this manual describes the command language, system routines, error messages, and terms of the Version 5.3-1 VMS Security Enhancement Service software.

Revision/Update Information: This manual supersedes the previous version, Version 5.2, of the *VMS SES User's Guide*.

Operating System and Version: VMS Version 5.3-1

Software Version: SEVMS Version 5.3-1

June 1990

The information in this document is subject to change without notice and should not be construed as a commitment by Digital Equipment Corporation.

Digital Equipment Corporation assumes no responsibility for any errors that may appear in this document.

Any software described in this document is furnished under a license and may be used or copied only in accordance with the terms of such license. No responsibility is assumed for the use or reliability of software or equipment that is not supplied by Digital Equipment Corporation or its affiliated companies.

Restricted Rights: Use, duplication, or disclosure by the U.S. Government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013.

© Digital Equipment Corporation 1990. All rights reserved.

Printed in U.S.A.

The Reader's Comments form at the end of this document requests your critical evaluation to assist in preparing future documentation.

The following are trademarks of Digital Equipment Corporation:

DEC	DIBOL	UNIBUS
DEC/CMS	EduSystem	VAX
DEC/MMS	IAS	VAXcluster
DECnet	MASSBUS	VMS
DECsystem-10	PDP	VT
DECSYSTEM-20	PDT	
DECUS	RSTS	
DECwriter	RSX	

This document was prepared with VAX DOCUMENT, Version 1.2.

Contents

PREFACE

v

CHAPTER 1 INTRODUCTION TO SEVMS

1-1

1.1	OVERVIEW	1-1
1.1.1	Description of SEVMS _____	1-1
1.1.2	Intent of SEVMS _____	1-1
1.1.3	Advantages of SEVMS _____	1-1
<hr/>		
1.2	COMPLEMENTARY SECURITY TECHNIQUES OF VMS AND SEVMS	1-2
<hr/>		
1.3	MANDATORY ACCESS CONTROLS	1-2
1.3.1	Secrecy Levels _____	1-3
1.3.2	Secrecy Categories _____	1-3
1.3.3	Integrity Levels and Categories _____	1-3
1.3.4	Classification Labels _____	1-4
<hr/>		
1.4	MANDATORY ACCESS CONTROL RULES	1-4
1.4.1	Access Rules Description _____	1-5
1.4.2	Access Rules and Privileges _____	1-5
<hr/>		
1.5	RELATIONSHIP BETWEEN DISCRETIONARY AND MANDATORY ACCESS CONTROLS	1-6
1.5.1	Mandatory Access Types _____	1-6
<hr/>		
1.6	LOGGING IN	1-7
<hr/>		
1.7	DISPLAYING SESSION CLASSIFICATION	1-8
<hr/>		
1.8	CLASSIFYING DIRECTORIES AND FILES	1-8
1.8.1	Determining File Classification _____	1-9
1.8.2	Determining Directory Structure _____	1-9
1.8.3	Organizing Directories and Files _____	1-9
1.8.4	Setting the Classification of Directories and Files _____	1-11

CHAPTER 2	DCL COMMANDS	2-1
	ANALYZE/AUDIT	2-2
	SET	2-5
	SET AUDIT	2-8
	SET CLASS	2-11
	SET CLASS/NODE	2-13
	SET CLASS/SERVER	2-16
	SET CLASS/TERMINAL	2-18
	SET DEVICE/CLASS	2-20
	SET DIRECTORY/CLASS	2-21
	SET FILE/CLASS	2-22
	SET TEMPLATE	2-23
	SHOW AUDIT	2-26
	SHOW CLASS	2-28
	SHOW TEMPLATE	2-33
	DIRECTORY	2-36
	INITIALIZE	2-38

CHAPTER 3	PROGRAMMING INFORMATION	3-1
------------------	--------------------------------	------------

3.1	CLASS BLOCK FORMATS	3-1
3.2	SYSTEM SERVICES	3-2
	3.2.1 SEVMS Mandatory Access Control Items in VMS System Services	3-2
	3.2.1.1 \$CHKPRO System Service • 3-2	
	3.2.1.2 \$GETUAI System Service • 3-2	
	3.2.1.3 \$CREPRC System Service • 3-3	
	3.2.1.4 \$QIO System Service — ACP-QIO Interface • 3-4	
	3.2.2 SEVMS System Service Routines	3-4
	3.2.2.1 Introduction • 3-4	
	3.2.2.2 Item Lists • 3-4	
	\$PARSE_CLASS	3-7
	\$FORMAT_CLASS	3-9
	\$CHANGE_CLASS	3-11
3.3	SEVMS BINARY AUDIT RECORD FORMAT	3-15
	3.3.1 SEVMS Audit Record Types and Subtypes	3-15
	3.3.2 SEVMS Audit Data Packets	3-15

APPENDIX A	SEVMS SYSTEM MESSAGES AND RECOVERY PROCEDURES	A-1
-------------------	--	------------

GLOSSARY	Glossary-1
-----------------	-------------------

INDEX

FIGURES

1-1	Directory Structure Example _____	1-11
3-1	Type 0 Class Block Format _____	3-1
3-2	Type 1 Class Block Format _____	3-2

TABLES

1-1	Mandatory Access Control Rules _____	1-5
3-1	SEVMS System Service Items _____	3-5
3-2	SEVMS-unique Audit Record Types and Subtypes _____	3-15
3-3	SEVMS Audit Data Packets _____	3-15

Preface

This document introduces the VMS Security Enhancement Service and describes the command language interface, system routines, error messages, and terms associated with it.

The VMS Security Enhancement Service (VMS SES) is a software security consulting package. It provides many features of mandatory access controls and security auditing for the VMS operating system.

The VMS SES software security consulting package is composed of the following components:

- Services performed by a DIGITAL consultant
- Licensed software
- Documentation

VMS SES provides the services of a trained DIGITAL consultant who supports the customer in several areas, such as: assisting in planning security policies and controls, training users, and installing the licensed software.

The licensed software component of this product is called SEVMS. SEVMS provides a tool set for devising a system-wide security policy to help safeguard users, data, and software from security threats. Since this manual describes the features of the licensed software, the term SEVMS is used throughout this manual to reference this software. SEVMS is also the VMS facility name for the licensed software and is used as a prefix for many of the software components.

A documentation set which describes the SEVMS software and how it is installed, used, and managed is provided with the VMS SES package.

Intended Audience

This manual is intended for all users of an SEVMS system. It is assumed that the users of this manual have a general working knowledge of VMS.

Document Structure

The information in this manual is divided into the following chapters:

- Introduction to VMS Security Enhancement Service — This chapter contains general information about SEVMS, information about complementary security techniques, mandatory access controls, access rules, logging into a system, classifying directories and files, and propagation of classification.
- DCL Commands — This chapter describes the DCL commands which are used by SEVMS and explains how these commands operate.

Preface

- **Programming Information** — This chapter provides programming information, including an explanation of the SEVMS class block format and binary audit record format, descriptions of the system service routines that are employed by SEVMS, and a description of SEVMS mandatory access control items which are used with VMS System Services.
- **System Messages** — This section contains system messages which are unique to SEVMS.
- **Glossary** — This section explains the terms most commonly used in SES documentation.

Associated Documents

This manual should be used in conjunction with the other manuals of the SES document set and the manuals of the VMS document set. References will be made throughout this manual to VMS SES manuals and VMS manuals.

SES Document Set

This manual is one of three manuals that form the VMS Security Enhancement Service (SES) document set. This document set consists of the following manuals:

- *VMS SES User's Guide* — This manual describes the mandatory protection mechanisms provided by the SEVMS software, the interaction of these mechanisms with VMS discretionary protection mechanisms, and the use of commands and utilities which are unique to SEVMS. It is intended for all SEVMS users.
- *VMS SES Security Manager's Guide* — This manual describes the configuration, management, and operation of SEVMS. It is intended for use by system administrators and security officers. This manual assumes that the reader is familiar with basic VMS security practices and the VMS documentation which describes VMS security.
- *VMS SES Installation Guide and Release Notes* — This manual is intended as a supplemental manual of the SES documentation set. It provides information concerning the installation (but not configuration) of SEVMS on a VMS system. It also contains release notes which summarize omitted features, resolved problems, new features, and known problems and restrictions for the current release of the SEVMS software.

Together, these manuals form complete documentation about SEVMS. For information about related VMS features and functions, the user should refer to the manuals of the VMS document set.

VMS Documentation Set

The VMS documentation set has two main divisions:

- VMS Base Documentation Set
- VMS Extended Documentation Set

The VMS Base Documentation Set is a desk-top set for users of small standalone systems and low-end Local Area VAXclusters, and for general users of large VAX systems. The Base Documentation Set contains concise, easy to find, information about performing day-to-day tasks. This documentation set contains the following components:

- Overview of VMS Documentation
- VMS New Features Manual
- VMS General User's Manual
- VMS System Manager's Manual
- VMS Mini-Reference Manual
- VMS License Management Manual

The VMS Extended Documentation Set is a full documentation set for users who need more detail about any VMS component to perform daily tasks. The Extended Documentation Set also meets the needs of system managers of large VAX systems and of system and application programmers.

This documentation set contains the following components:

- General User Subkit
- System Management Subkit
- Programming Subkit

These manuals are supplemented by several other forms of VMS documentation: Release Notes, Obsolete Features Kit, Software Installation and Operations Guides, online help information, and other optional documentation.

Refer to the *Overview of VMS Documentation* booklet in the VMS documentation set for complete information about the VMS documentation set.

Relationship Between VMS and SEVMS Documentation

The documentation for SEVMS is intended to be used along with the documentation for VMS. While the SES documentation set addresses issues specific to the SEVMS product, issues of a more general nature pertaining to VMS are addressed in the VMS documentation set. Therefore, you can consider the manuals of the SES document set to be an extension of your existing VMS document set. As such, SES manuals do not repeat information already contained in existing VMS documentation. Instead, references are made throughout SES manuals to several of the manuals in the VMS document set, when appropriate. The following VMS documentation is most frequently referenced by the SES manuals:

- *VMS System Management Subkit*
- *Guide to VMS System Security*
- *VMS DCL Dictionary*
- *VMS Release Notes*
- *VMS Audit Analysis Utility Manual*

Conventions

This section describes the VMS and SEVMS conventions which are used in this manual.

VMS Conventions Used in This Manual

Throughout this manual, the following standard conventions are used in examples of commands:

Convention	Meaning
[]	Square brackets indicate that the enclosed item is optional.
{ }	Braces enclose a list from which one element must be chosen.
<>	Angle brackets indicate that item is to be replaced by a specific instance of the named quantity.
	The OR symbol separates alternatives within braces or brackets.
...	An ellipsis indicates that the preceding item(s) can be repeated one or more times.
:=	A "colon equals" indicates the item to its left is defined as the item to its right.

Unless otherwise indicated in the examples, commands are terminated by pressing the **Return** key.

Colons (:) and equals signs (=) are used interchangeably in descriptions of DCL command qualifiers.

SEVMS Conventions Used in This Manual

SEVMS mandatory access controls introduce a number of new protection attributes and relationships. Among these are the concepts of hierarchical *levels* and non_hierarchical *categories*. Categories form discrete mathematical *sets*.

The *operators* used to indicate the relationship between numeric quantities (*scalar*) differ from the operators used to indicate the relationship between non-numeric quantities (*sets*), although their meanings are similar. The operators used in this manual are described and compared in the following table.

Operator	Scalar Interpretation for Security Levels	Operator	Set Interpretation for Security Categories
$<$	is less than	\subset	is a proper subset of
\leq	is less than or equal	\subseteq	is a subset of
$=$	is equal to	\equiv	is identical to
$>$	is greater than	\supset	is a proper superset of
\geq	is greater than or equal	\supseteq	is a superset of
\neq	is not equal to	\neq	is not identical to

In informal discussions of the relationship between two classifications, the scalar relationships may be used to refer to both the scalar (level) and set (categories) portions of the classification. For instance, the informal statement "A's classification is equal to B's" means "A's level = B's level AND A's categories \equiv B's categories".

Dominates describes a relationship between two classifications. "A's classification dominates B's" means "A's level \geq B's level AND A's categories \supseteq B's categories".

1

Introduction to SEVMS

This chapter introduces and defines the software of the VMS Security Enhancement Service (VMS SES), which is referred to in this manual as SEVMS.

1.1 Overview

This section briefly describes the nature of SEVMS, its intent, and its advantages.

1.1.1 Description of SEVMS

SEVMS implements a *mandatory* (i.e. *non-discretionary*) access control mechanism. The most distinguishing characteristic of the SEVMS mandatory access control mechanism is that it is an implementation of a security policy which is *beyond direct user control*. This security policy is centrally and uniformly established by the system security manager (often the system manager). SEVMS is responsible for enforcing the security policy established by the security manager.

1.1.2 Intent of SEVMS

It is important to note that the SEVMS mandatory controls do not replace the familiar VMS discretionary access controls (such as Access Control Lists). Instead, SEVMS mandatory controls are used *in addition to* standard VMS discretionary controls, and *augment* VMS protection mechanisms. Therefore, SEVMS is intended to provide the system security manager with a means to enforce an additional system-wide mandatory security policy.

1.1.3 Advantages of SEVMS

The use of SEVMS mandatory access controls enables the security manager to classify users and data with different levels of sensitivity. By classifying users, SEVMS ensures the following:

- Users cannot read data unless their classification permits it.
- Users cannot write data with a new classification that would grant read access to users who could not previously read the data.

In addition to the advantages of classifying users, SEVMS also provides the following advantages:

- It provides auditing of attempts to compromise mandatory access controls.

- It restricts certain users to certain terminals, based on classification.
- It restricts printed output to certain printers, based on classification.
- It restricts creation of files on certain disks, based on classification.
- It provides a uniform mechanism for the sensitivity labeling of print jobs.

1.2 Complementary Security Techniques of VMS and SEVMS

As mentioned at the beginning of this chapter, SEVMS security features are *not* meant to replace standard VMS security features. Instead, the security features of SEVMS are provided in addition to those standard features of VMS. Before implementing SEVMS security features, it is important that the security manager be very familiar with VMS security features and how they are used. Therefore, the material contained in the *Guide to VMS System Security* should be thoroughly read and understood.

1.3 Mandatory Access Controls

Mandatory access controls in SEVMS are used to control access between *subjects* and *objects* in a system. An example of a subject is a process. (In fact, under SEVMS, processes are the only subjects.) An example of an object is a file. Subjects and objects can be assigned *classification labels* which are made up of a combination of hierarchical *secrecy levels* and non-hierarchical *secrecy categories*. Classification labels are discussed in more detail in Section 1.3.4 of this manual.

The SEVMS software provides the following mandatory access control elements:

- 256 secrecy levels
- 128 secrecy categories
- 256 integrity levels
- 64 integrity categories

Subjects, objects, and classification labels are further discussed in "Chapter 2, Overview of SEVMS" of the *VMS SES Security Manager's Guide*. Mandatory access controls, secrecy levels, and secrecy categories are discussed in greater detail in "Chapter 4 - Mandatory Access Control and the User" and "Chapter 5 - Mandatory Access Control and the Security Manager" of the *VMS SES Security Manager's Guide*.

The remainder of this section discusses the following topics:

- Secrecy levels and categories
- Integrity levels and categories
- Classification labels

1.3.1 Secrecy Levels

SEVMS secrecy levels are hierarchical - they range in value from 0 to 255, with 0 representing the lowest level and 255 representing the highest. A lower secrecy level indicates a lower classification; a higher secrecy level represents a higher classification. Secrecy levels can always be specified as numeric values; however, secrecy levels are normally represented symbolically. For example, the secrecy level 0 might be symbolically represented by UNCLASSIFIED, the secrecy level 10 might be represented by CONFIDENTIAL, and a secrecy level of 255 might be TOP SECRET, and so on. The assignments are made by the system manager or security manager.

1.3.2 Secrecy Categories

Secrecy categories are non-hierarchical. As with secrecy levels, secrecy categories can be represented numerically (1 through 128), or they can be represented symbolically. Secrecy categories are used to assign non-hierarchical attributes to an object. Secrecy categories are especially useful when there is a need to create separate compartments for information. Because secrecy categories are disjoint, no category can be considered more classified than another; only the presence or absence of a particular secrecy category matters.

For instance, a secrecy category RED document is more classified than a secrecy category BLUE document because the BLUE document does not have the RED secrecy category. But, the reverse is also true; the same can be said of the BLUE document with respect to the RED document.

To avoid the confusion of the situation described above, the term *dominate* should be used when comparing two classifications. For example, if you are comparing classifications "A" and "B", you would use the following terminology: The statement "*A's classification dominates B's*" means that "A's" secrecy level is greater than "B's" and "B's" set of secrecy categories is a subset of "A's". Although "dominate" is the more accurate term, comparative terms such as "greater than" are often used informally to mean the same thing.

1.3.3 Integrity Levels and Categories

There are 256 *integrity levels* and 64 *integrity categories*. Although SEVMS provides controls for integrity, the consequences of its use with VMS are not well understood. Therefore, DIGITAL supports the detailed functionality of SEVMS in regards to integrity controls, but cannot make any assurances as to the overall consequences of using those controls. In particular, **the VMS Security Enhancement Service does not provide assistance in the use of integrity at this time**. Integrity has been omitted from this discussion of mandatory access controls for the sake of simplicity. See the *VMS SES Security Manager's Guide* for more information on integrity.

1.3.4 Classification Labels

A *classification label* (also referred to as "label" in this manual) consists of a secrecy level and some combination of secrecy categories. Labels can be assigned to the following objects and subjects:

- ODS-2 files
- ODS-2 disk volumes
- Mailboxes
- Shared logical name tables
- Global sections
- Disk devices
- Logical name tables
- Magnetic tape devices
- Terminal devices
- Printer devices
- Processes
- Queues

Note: Any device can be labeled - SEVMS will restrict access to that device at the QIO level; however, SEVMS provides specific multilevel device support for only the devices listed above.

The following example illustrates the assignment of a label.

User Jones may log in at the level SECRET with categories RED, WHITE, and BLUE as follows:

```
USERNAME: JONES/SECURITY=(LEVEL:SECRET,CATEGORY:(RED,WHITE,BLUE))
PASSWORD:
```

```
Welcome to VMS V5.3-1...
```

```
.
.
.
```

In this case, the specified classification label is attached to the process JONES for the lifetime of the process.

1.4 Mandatory Access Control Rules

This section describes the rules of mandatory access control and the privileges which affect these rules.

1.4.1 Access Rules Description

Mandatory access control rules are straightforward and simple. Put informally, an unprivileged user is allowed to do the following:

- READ DOWN (read a lower classification)
- WRITE UP (write to a higher classification)
- READ/WRITE EQUAL (read and write to an equal classification)

These rules are summarized in more formal terms in Table 1–1.

Table 1–1 Mandatory Access Control Rules

If your process classification	Permitted access is
DOMINATES the object classification	READ ONLY
is DOMINATED BY the object classification	WRITE ONLY†
is EQUAL TO object classification	READ and WRITE

†Some objects, particularly files, cannot be accessed WRITE ONLY.

1.4.2 Access Rules and Privileges

The mandatory access control rules can be circumvented by users with certain privileges.

SEVMS does not remove or limit existing VMS privileges. Users with any of the ALL privileges (as defined in the *Guide to VMS System Security*), can manage to BYPASS the mandatory access controls, just as they can bypass the discretionary access controls.

The privileges which directly affect mandatory access control rules are as follows:

- DOWNGRADE - Allows a process to write to a lower secrecy object or to lower an object's classification.
- SECURITY - Allows a process to set a multilevel classification and to turn on and off security auditing.
- BYPASS - Bypasses all protection checks.
- VOLPRO - Bypasses volume protection checks.
- UPGRADE - Allows a process to write to a higher integrity object or to raise the integrity of an object.
- READALL - Allows read access to everything.

To be assured that access rules are enforced, it is important that the security manager be familiar with VMS privileges and restrict their use.

1.5 Relationship Between Discretionary and Mandatory Access Controls

In the SEVMS implementation of mandatory access controls (MAC), there are two types of access: *read*, and *write*. In the VMS (and thus SEVMS) implementation of discretionary access controls (DAC), there are at least 7 access types: READ, WRITE, EXECUTE, DELETE, CONTROL, PHYSICAL, and LOGICAL.

There are no fixed relationships between the MAC and DAC access types; whether a DAC access type requires a particular MAC access type depends upon the particular object and operation.† This can be confusing, unless you understand the interpretations of the DAC and MAC access types.

The DAC access types are described in Section 4.2.7 of the *Guide to VMS System Security*. The MAC access types are described below, in Section 1.5.1.

Reminder: Both MAC and DAC checks must be passed before access to an object is allowed.

1.5.1 Mandatory Access Types

There are two MAC (mandatory access controls) access types, *read* and *write*.

These MAC access types have the following interpretations for all objects:

READ

The right to observe the contents and attributes of an object.

WRITE

The right to modify the contents and attributes of an object.

"MAC access types" refer to the *kind* of operation being performed on an object, not to the DAC access types. For instance, to run a program, you need MAC READ access to the image as well as DAC EXECUTE access. In this case, running the program reads the executable image into the processes' address space, allowing the user to see it - so MAC READ access is required.

Note: VMS (thus SEVMS) does not support write-only access to some objects, particularly files. If write-only access is not supported for an object, then both READ and WRITE MAC access is required to write to the object.

MAC access types, unlike the DAC access types, are not explicitly associated with object protection codes or ACLs. For instance, you can't grant a user mandatory READ access to an object by way of an ACL. It is the relationship between the subject's and the object's classifications and the subject's privileges which determine the types of MAC access allowed. Refer to Section 1.4 of this manual for information about this topic.

† This is why the \$CHKPRO system service has two different items which refer to read and write access. The DAC access type is passed in the CHP\$_ACCESS; the MAC access type is passed in CHP\$_FLAGS.

1.6 Logging in

Users can be assigned a range of classifications by the system manager or security manager. However, a user process can operate at one classification at a time only. The classification of a session is specified when a user logs in by using the /SECURITY qualifier with the user name.

In the following example, user Jones logs in and specifies a classification of SYSTEM_LOW for this session:

```
Username: Jones /SECURITY=(LEVEL:SYSTEM_LOW)
Password:

Welcome to VMS V5.3-1...
```

If the user does not specify the /SECURITY qualifier when logging in, the session classification defaults to the user's highest authorized classification.

The user cannot specify a classification when logging in to a DECwindows session on a VAXstation. Users must always log in at their *default* classification. Furthermore, in this version of SEVMS, users are only allowed to log in to an *unclassified* DECwindows session (i.e. LEVEL=0, CATEGORIES=NONE). Attempting to log in to a classified DECwindows session causes the following error message to be displayed:

```
Not supported
```

If an attempt to log in fails for reasons related to mandatory access controls, the following message is returned:

```
User authorization failure
```

This message does not give the explicit reason for the rejection of the log-in. This prevents supplying any information to an unauthorized person who is making a determined attack on the system.

Some examples of reasons you may receive this message are:

- You attempted to log in at a classification for which you have no authorization.
- You incorrectly specified a classification.
- The classification that you requested is incompatible with the classification of the terminal you are attempting to log in on.
- You explicitly specified a classification when logging in to a CAPTIVE account.

1.7 Displaying Session Classification

At times, it may be necessary or useful to display the classification of the session you have logged in to. To display the classification of your session, use the `SHOW CLASS/PROCESS` command.

For example, you enter the command as follows:

```
$ SHOW CLASS/PROCESS
```

The type of information that is returned as a result of entering this command is illustrated in the following example.

```
Object type: process, Object name: JONES, on 13-MAY-1989 06:33:53.58  
Class: SECRECY=(LEVEL=FIUO,CATEGORY=(NONE))
```

1.8 Classifying Directories and Files

This section describes the method of classifying directories and files.

Who Should Classify Directories and Files?

Depending upon the site, either the security manager, system manager, or the user may have the task of classifying each user's directories and files when SEVMS is installed.

When Should Directories and Files be Classified?

The classification of directories and files must be done when SEVMS is first installed on the system, or when new accounts are added on disks. In the case of an existing SEVMS system or account, SEVMS automatically classifies newly created files and directories with the same classification of the process creating the file or directory.

What Is the Method of Classifying Directories and Files?

Classifying directories and files requires the following steps:

- 1 Determine the classification of each file to be classified.
- 2 Determine a directory structure for these files (i.e. how files should go into directories).
- 3 Organize the directories and files according to the way that you've determined they are to be classified.
- 4 Set the classification of the directories and files.

The above steps are described in detail in Section 1.8.1, Section 1.8.2, Section 1.8.3, and Section 1.8.4, which follow.

Note about Propagation of Classification

As mentioned above, when you are dealing with an already existing SEVMS system or account, newly created files and directories are given, by default, the classification of the process you are currently logged in at. Therefore, when you create a file or directory, it acquires the classification of your process, not the classification of the directory in which the file or directory file resides.

1.8.1 Determining File Classification

Examine the files and directories that you wish to classify. Determine which files should be classified at a particular secrecy level according to the needs of your site.

1.8.2 Determining Directory Structure

After determining how you are going to classify your files, you need to determine how these files are to be arranged in your directory (i.e. the directory structure).

To determine a directory structure for the files which you intend to classify, you need to establish the following:

- What directories should be created?
- What classification should each directory have?
- Which files should go into which directories?

After you have established the way you are going to organize your files and directories, you are ready to go on to the next step.

1.8.3 Organizing Directories and Files

When organizing directories and files, keep the following points in mind:

- Directories and files must be organized into a hierarchy that corresponds to the hierarchy of secrecy levels (i.e. lower level directories should have higher classifications than higher level directories).
- To access a file, your process must have *read access* to all the directories in the directory string.

These two points have the following important implication. **A directory should never have a subdirectory with a classification that is lower than the classification of the parent directory.**

To further clarify this idea, consider the following example.

Suppose that your account contained the following directory structure:

```
[HOTDOG.BASEBALL.JUNKFOOD]
```

These directories are classified as SYSTEM_LOW, TOP_SECRET, and SYSTEM_LOW, respectively.

```

[HOTDOG] (system_low classification)
  |
[HOTDOG.BASEBALL] (top_secret classification)
  |
[HOTDOG.BASEBALL.JUNKFOOD] (system_low classification)

```

Introduction to SEVMS

In this example, if your current process is operating at `SYSTEM_LOW`, you would be unable to access the `SYSTEM_LOW [...JUNKFOOD]` directory, since your process does not have *read access* to the preceding `TOP_SECRET [...BASEBALL]` directory.

The proper way to organize the directory structure in the above example is to make the `TOP_SECRET [...BASEBALL]` directory a subdirectory to the `SYSTEM_LOW [...JUNKFOOD]` directory, as shown below:

```
[HOTDOG.JUNKFOOD.BASEBALL]
```

Now, the secrecy levels of these directories are organized in the following order: `SYSTEM_LOW`, `SYSTEM_LOW`, `TOP_SECRET`, respectively.

```
[HOTDOG] (system_low classification)
|
[HOTDOG.JUNKFOOD] (system_low classification)
|
[HOTDOG.JUNKFOOD.BASEBALL] (top_secret classification)
```

With the directory structure organized in this way, if your current process is operating at `SYSTEM_LOW`, you can access both of the directories that are classified at `SYSTEM_LOW`.

As you go down in the directory structure, the secrecy level should increase. However, you can have different secrecy levels at the same level in the directory structure. For example, your log-in directory can have `SYSTEM_LOW` and `CONFIDENTIAL` subdirectories.

Therefore, the directories in the original example could also have been organized as follows:

```
[HOTDOG.JUNKFOOD]
[HOTDOG.BASEBALL]
```


In this case, the higher level directory, `HOTDOG`, is classified at `SYSTEM_LOW`; the subdirectory, `JUNKFOOD`, is classified at `SYSTEM_LOW`; and the subdirectory, `BASEBALL`, is classified at `TOP_SECRET`.

```
[HOTDOG] (system_low)
|
-----
|
[HOTDOG.JUNKFOOD] (system_low)           [HOTDOG.BASEBALL] (top_secret)
```

Figure 1-1 contains another example of a possible directory structure. In this example, the classification appears abbreviated after the directory name (`SYSTEM_LOW` is abbreviated to `SL`, `TOP_SECRET` to `TS`).

Note that `[LOCAL.JUNKFOOD]` and `[LOCAL.PROJECT]` exist at the same directory level, but have different classifications.

Figure 1-1 Directory Structure Example



1.8.4 Setting the Classification of Directories and Files

After organizing your directories and files, you are ready to set their classification. To classify a file or directory, you must have mandatory READ and WRITE access, and discretionary CONTROL access to the object. Also, keep in mind that if you classify a file with a classification that is not in the classification range of your account, you may need privileges to access that file.

Use the following order when setting the classification of directories and files:

- 1 Set the classification of the files within the directories.
- 2 Set the classification of each directory.

Classifying Files

To set the classification of a file, use the SET CLASS command. For example, to classify all the files in the default directory at FIUO, you would use the following command:

```
$ SET CLASS *.* /* /SECURITY=(LEVEL:FIUO)
```

Classifying Directories

To set a directory classification, use the SET CLASS command. For example, to set the classification of the directory [SOCRATES.PROJECT], you would use the following command:

```
$ SET CLASS /SECURITY=(LEVEL:TOP_SECRET) [SOCRATES]PROJECT.DIR
```


2

DCL Commands

This chapter contains descriptions of all SEVMS DCL commands. SEVMS DCL commands are existing VMS DCL commands which have been modified, and new DCL commands which have been added, to provide users with new functionality for the SEVMS environment.

ANALYZE/AUDIT

The ANALYZE/AUDIT command analyzes the contents (audit records) of an audit archive file. Only SEVMS-specific usage of this command is explained in this section. For a full description of ANALYZE/AUDIT, refer to the *VMS Audit Analysis Utility Manual* and the *Guide to VMS System Security*.

FORMAT **ANALYZE/AUDIT** *file-spec[,...]*

restrictions

- Refer to the *VMS Audit Analysis Utility Manual* and the *Guide to VMS System Security* for additional restrictions.
- The **/FACILITY=SEVMS** qualifier is required when using **/EVENT_TYPE**.

PARAMETERS *file-spec[,...]*

Specifies the name of the audit archive file. Refer to the *VMS Audit Analysis Utility Manual* and the *Guide to VMS System Security* for details.

DESCRIPTION

The ANALYZE/AUDIT command enables the user to analyze the audit records contained in an audit archive file.

The information provided in this section pertains only to the use of the ANALYZE/AUDIT command in relation to SEVMS. A full description of ANALYZE/AUDIT is provided in the *VMS Audit Analysis Utility Manual* and the *Guide to VMS System Security*.

The ANALYZE/AUDIT command is basically the same for both VMS and SEVMS, with the exception that SEVMS includes additional SEVMS-specific qualifiers and some additional SEVMS-specific keywords and criteria. Also, for SEVMS, when the **/SUMMARY** qualifier is used with the ANALYZE/AUDIT command, SEVMS-related information is displayed in addition to standard VMS information.

Other than these SEVMS-related differences, both VMS and SEVMS use the ANALYZE/AUDIT command in exactly the same way. SEVMS users can utilize all VMS commands and qualifiers, as well as the additional SEVMS-specific qualifiers and keywords.

Because of this, only SEVMS-specific usage of the ANALYZE/AUDIT command is explained in this command section. The following areas of the ANALYZE/AUDIT command are new or changed for SEVMS:

- **/FACILITY=SEVMS** qualifier added

- **/EVENT_TYPE** qualifier — The SEVMS-specific keywords PRINTED_FILE, LABEL_BYPASS, CHANGE_CLASS, and ALL have been added to the /EVENT_TYPE qualifier.
- **/SELECT** qualifier — The SEVMS-specific keywords SYMBIONT_PROCESS_ID and QUEMGR_JOB_NUMBER have been added to the /SELECT qualifier.
- **PRIVILEGES_USED** keyword of /SELECT qualifier — The SEVMS-specific criteria UPGRADE and DOWNGRADE have been added to PRIVILEGES_USED keyword of the /SELECT qualifier.

QUALIFIERS

/SELECT=(keyword[,...])

The /SELECT qualifier specifies the criteria to be used when selecting event records. The following SEVMS-related criteria can be specified:

Keyword	Description
PRIVILEGES_USED=(privs[...])	Specifies the privileges of the process to be used in selecting event records. The following SEVMS privileges can be specified: UPGRADE DOWNGRADE
SYMBIONT_PROCESS_ID	Specifies the process ID for the SEVMS print symbiont.
QUEMGR_JOB_NUMBER	Specifies the number of the print job.

/EVENT_TYPE=(event-type[,...])

The /EVENT_TYPE qualifier specifies the general class of event to be used in making a selection. The /FACILITY=SEVMS qualifier is required when using this command qualifier. The following SEVMS keywords are available with this qualifier:

Record Type	Meaning
PRINTED_FILE	Selects attempts to print files.
LABEL_BYPASS	Selects attempts to bypass page labeling using the PRINT/PASSALL command.
CHANGE_CLASS	Selects attempts to change the classification of objects using SET CLASS command (i.e. \$CHANGE_CLASS system service).
ALL	Selects all events. Displays all SEVMS information in addition to all VMS information. Use with /FACILITY=SEVMS to display only SEVMS information.

/FACILITY=SEVMS

The SEVMS-specific qualifier /FACILITY=SEVMS is used with the /EVENT_TYPE qualifier and is required for specifying SEVMS event types. The syntax for using this command is shown below.

ANALYZE/AUDIT/FACILITY=SEVMS/EVENT_TYPE=sevms_event_type-keyword filename

ANALYZE/AUDIT

EXAMPLES

1 \$ ANALYZE/AUDIT/FACILITY=SEVMS/EVENT_TYPE=PRINTED_FILE AUDIT.LOG

This example produces a report which includes all audit messages resulting from attempts to print files. It specifies that the information be selected from the audit archive file named AUDIT.LOG. Note that the /FACILITY=SEVMS qualifier is included in the command line (it is required).

2 \$ ANALYZE/AUDIT/FULL/SELECT=PRIVILEGES_USED=UPGRADE -
_ \$ SYS\$MANAGER:SECURITY_AUDIT.AUDIT\$JOURNAL

This example produces a report which selects all records written to the security audit log file that were generated by events through the use of the UPGRADE privilege.

3 \$ ANALYZE/AUDIT/SELECT=SYMBIONT_ID=150 AUDIT.LOG

Date / Time	Type	Subtype	Node	Username	ID
25-SEP-1989 18:18:29.75	PRINT	PRINT_FAIL	TURBOII	RUSNERS	00000150
25-SEP-1989 18:40:21.08	PRINT	PRINT_FAIL	TURBOII	RUSNERS	00000150
25-SEP-1989 18:46:27.36	PRINT	PRINT_FAIL	TURBOII	RUSNERS	00000150
25-SEP-1989 19:23:09.75	PRINT	PRINT_FAIL	TURBOII	RUSNERS	00000150
25-SEP-1989 19:37:55.73	PRINT	PRINT_FAIL	TURBOII	RUSNERS	00000150
26-SEP-1989 07:27:43.47	PRINT	PRINT_FAIL	TURBOII	RUSNERS	00000150
26-SEP-1989 07:36:01.49	PRINT	PRINT_SUCC	TURBOII	RUSNERS	00000150

This example produces a report which selects all records written to the security audit log file that have a symbiont ID number of 150.

4 \$ \$ANALYZE/AUDIT/FACILITY=SEVMS/EVENT_TYPE=LABEL_BYPASS AUDIT.LOG

Date / Time	Type	Subtype	Node	Username	ID	Term
6-MAR-1990 14:42:24.59	PRINT	PRINT_SUBTYP_NOP	TURBO	SYSTEM	00000174	

This command specifies that SEVMS audit records which contain attempts to bypass the page labeling on files through use of the PRINT/PASSALL command be displayed for analysis. It specifies that the information be selected from the records in audit archive file named AUDIT.LOG. In this case, the AUDIT.LOG file contained only one record of such an attempt: it occurred on node TURBO, by user SYSTEM, on the day and time shown.

5 \$ ANALYZE/AUDIT/SELECT=SYMBIONT_ID=* AUDIT.LOG

This example uses a wildcard to select all records which have a SYMBIONT_ID. This, in effect, produces a report which selects all records written to the security audit log file resulting from print events.

SET

The SET command defines or changes classifications associated with an object (SET CLASS), defines the templates to be associated with a category (or categories) of print jobs (SET TEMPLATE), and audits files according to classification (SET AUDIT). Equivalent commands for the SET CLASS command can be given using SET DEVICE, SET DIRECTORY, and SET FILE with SEVMS-specific qualifiers; however, for consistency, use of SET CLASS is recommended.

FORMAT **SET** *option/SECRECY=string parameters*

restrictions

- The qualifier /SECRECY is mandatory for SEVMS SET commands.

PARAMETERS *See the individual SET command options.*

DESCRIPTION The SET command options for SEVMS are briefly described in the following table. A full description of each SET command option is included in the following pages of this section. The SEVMS SET commands augment the standard VMS SET commands.

Option	Function
AUDIT	Perform SEVMS auditing functions which allow access to classified files to be audited.
CLASS	Modify the classification of an object.
DEVICE	Modify the classification of a device.
DIRECTORY	Modify the classification of a directory.
FILE	Modify the classification of one or more files.
TEMPLATE	Associate a printed template to be output with all print jobs possessing certain attributes.

QUALIFIERS

/SECRECY

Used with SET AUDIT to indicate mandatory access control auditing. See the description of the SET AUDIT command for more information.

/SECRECY=class-string

The /SECRECY=class-string qualifier is used with the SET CLASS, SET DEVICE/CLASS, SET DIRECTORY/CLASS, and SET FILE/CLASS commands. This qualifier is not used with the SET AUDIT command (see the preceding /SECRECY qualifier description).

Note: The maximum length for a qualifier value in VMS Version 5.3-1 is 256 characters. If a class-string longer than this must be specified, use the /SQn qualifiers which are described in this section.

The /SECURITY=class-string qualifier specifies a secrecy level and/or categories, or a range of secrecy levels and/or categories. SECURITY privilege is needed to set a classification to a range. DOWNGRADE privilege is needed to lower a secrecy classification.

/SECURITY Qualifier Syntax

```

secrty-qualifier := /SECURITY=(class-string)
class-string := {
  LEVEL= level-range |
  CATEGORY= category-range |
  LEVEL= level-range,
  CATEGORY= category-range
}
level-range := {
  level |
  (MAXIMUM:level) |
  (MINIMUM:level, MAXIMUM:level)
}
category-range := {
  category-list |
  (MAXIMUM:(category-list)) |
  (MINIMUM:(category-list),
  MAXIMUM:(category-list))
}
category-list := {
  category |
  (category [, ... ])
}

```

Notes:

If not entered, minimum ranges default to 0 or none.
Colons (:) and equals signs (=) can be used interchangeably in the qualifier.
If MAXIMUM is specified for a single level object, it is ignored.

See the specific command for more information.

/INTEGRITY=class-string

All SET commands which take a /SECURITY=class-string qualifier also take an /INTEGRITY=class-string qualifier. This qualifier is used to set integrity classifications. This qualifier is not documented in the individual SET commands to simplify their descriptions - since integrity is seldom used. UPGRADE or BYPASS privilege is needed to raise an integrity classification.

/SQ1="class-string part-1"

/SQ2="class-string part-2"

/SQ3="class-string part-3"

/SQ4="class-string part-4"

The /SQn qualifiers are used to specify class strings which are longer than 256 characters. A class string which exceeds 256 characters can be broken up into 2, 3, or 4 parts, each less than 256 characters, by using one or more of these qualifiers. Each part must be enclosed in quotation marks (""). The entire class string must be specified in a single command.

The format for the /SQn qualifier is:

SET *option* /SQ1="*string parameters*" /SQ2="*string parameters*" -
 _/SQ3="*string parameters*" /SQ4="*string parameters*"

EXAMPLES

```
1 $ SET CLASS/SQ1="(LEVEL=" -
  _$ /SQ2="SECRET,CAT" -
  _$ /SQ3="EGORY=RED)" FILE.DAT
```

This command qualifier enables the class string to be broken up into 3 parts.

disable the auditing by classification, both /SECURITY, /LEVEL and/or /CATEGORY, and either /ENABLE or /DISABLE are required.

/ALARM

SEVMS adds two keywords that can be used *only* with the /ENABLE=FILE_ACCESS and /DISABLE=FILE_ACCESS qualifiers of the SET AUDIT/ALARM command. The new keywords enable auditing of the use of DOWNGRADE or UPGRADE privilege to access a file. Note that they do *not* audit the use of SET CLASS to change the classification of a file.

The new keywords and the events for which they enable (or disable) alarms are:

New Keywords for FILE_ACCESS	Events audited
DOWNGRADE[:access[,access]]	Successful file access due to the use of the DOWNGRADE privilege
UPGRADE[:access[,access]]	Successful file access due to the use of the UPGRADE privilege

The DOWNGRADE privilege allows a user to write to a lower secrecy object; the UPGRADE privilege allows the user to write to a higher integrity object. See the SET AUDIT command description in the *VMS DCL Dictionary* for a description of SET AUDIT/ALARM and a list of the file_access keywords.

Note: To display the status of these alarms use the SHOW AUDIT command, not SHOW AUDIT/SECURITY.

/LEVEL=(level[,...])

Specifies the secrecy level or levels for which the specified event is, or is not, audited. An asterisk (*) can be used to indicate all levels.

One or more secrecy levels can be specified. Auditing is enabled or disabled for each level in the list; the list specifies a set of separate levels, not a range.

If the /SECURITY qualifier is used, then either /LEVEL, /CATEGORY, or both, must be used. You must specify /ENABLE or /DISABLE or both.

/CATEGORY=(category[,...])

Specifies the secrecy category or categories for which the specified event is, or is not, audited. An asterisk (*) can be used to indicate all categories.

One or more secrecy categories can be specified.

If the /SECURITY qualifier is used, then either /LEVEL, /CATEGORY, or both, must be used. You must specify /ENABLE, /DISABLE or both.

/DISABLE=events

Disables security auditing for the specified events. Events which can be disabled are the same as those which can be enabled. See the /ENABLE qualifier description for a list of the events to use with the /DISABLE qualifier.

SET AUDIT

/ENABLE=events

Enables security auditing for the specified events. Audit events consist of an event type and one or more event classes.

event-type:(event-class[,event-class])

The following event types can be specified when /ENABLE is used with /SECURITY:

event-type	Meaning
FILE_ACCESS	attempts to access files
PRINTED_FILE	attempts to print a file
LABEL_BYPASS	attempts to bypass the page labeling on a file by using the PRINT/PASSALL command
CHANGE_CLASS	attempts to change the classification of objects by use of the SET CLASS command or the \$CHANGE_CLASS system service

The following event classes may be specified when /ENABLE is used with /SECURITY:

event-class	Meaning
SUCCESS	the attempt succeeded
FAILURE	the attempt failed

When /ENABLE is used with /ALARM, all the normal event types may be used (see SET AUDIT in the *VMS DCL Dictionary*). In addition, the new keywords DOWNGRADE and UPGRADE are available with event type FILE_ACCESS.

EXAMPLES

1 \$ SET AUDIT/SECURITY/LEVEL=(SECRET, TOP_SECRET)/CATEGORY=(SENSITIVE) -
_ \$ /ENABLE=FILE_ACCESS=(SUCCESS, FAILURE)

This command enables auditing for all accesses to any file that has a level of SECRET or TOP_SECRET, as well as to any file with category SENSITIVE.

2 \$ SET AUDIT/SECURITY/LEVEL=TOP_SECRET/DISABLE=FILE_ACCESS=(FAILURE)

This command disables auditing for the unsuccessful access of a file that is level TOP_SECRET.

3 \$ SET AUDIT/ALARM/ENABLE=FILE_ACCESS:(DOWNGRADE, UPGRADE)

This command enables auditing of file accesses that succeed due to the possession of upgrade or downgrade privileges.

SET CLASS

The SET CLASS command changes the classification of an object.

FORMAT **SET CLASS** */SECURITY=class-string object-name*

restrictions

- The */SECURITY* qualifier is required.

PARAMETERS *object-name*

Specifies the object whose classification is being modified. Wildcards are allowed in the file names.

DESCRIPTION

If the object is not a file, the */OBJECT_TYPE* qualifier is required. If the */OBJECT_TYPE* qualifier is not specified, a file object type is assumed.

When using this command, it should be noted that SEVMS prevents changes in the classification of the following objects:

- File oriented devices (i.e. disk and tapes) with volumes mounted on them.
- Global sections backed by files that are mapped read/write.

QUALIFIERS

/SECURITY=class-string

See the description of this qualifier under the SET command.

/OBJECT_TYPE=type

Specifies the type of the object whose classification is being modified.

By default, a file object type is assumed. If the object is not a file, the */OBJECT_TYPE* qualifier is required. The following keywords may be specified with the */OBJECT_TYPE* qualifier:

Type	Meaning
FILE	Specifies that the object type is a file or a directory file.
DEVICE	Specifies that the object type is a device.
SYSTEM_GLOBAL_SECTION	Specifies that the object type is a system global section.
GROUP_GLOBAL_SECTION	Specifies that the object type is a group global section.
LOGICAL_NAME_TABLE	Specifies that the object type is a logical name table.
QUEUE	Specifies that the object type is a queue.

SET CLASS

EXAMPLES

1 \$ SET CLASS/SECURITY=(LEVEL:SECRET)/OBJECT_TYPE=DEVICE DLA0

The user changes the secrecy classification of the device DLA0 to a level of "SECRET".

2 \$ SET CLASS/SECURITY=(LEVEL:TOP_SECRET,CATEGORY=(RED)) FOO.BAR

The user changes the secrecy classification of the file FOO.BAR to level TOP_SECRET, category RED.

SET CLASS/NODE

This command does not check to verify the actual existence of the node being classified. This command requires SYSTEM privilege.

QUALIFIERS

/SECURITY=class-string

See the description of this qualifier under the SET command.

/LINK=(keyword)

The /LINK qualifier specifies the type of connections that are affected by the SET CLASS/NODE command.

There are four keywords that can be used with this qualifier: REMOTE, OUTGOING, INCOMING, NOCLASSIFICATION. These keywords are described in the following table.

The /LINK qualifier is required.

Link Type	Meaning
REMOTE	A SET HOST from the specified node can only log in within the indicated classification range. Other limitations on remote login continue to apply. (i.e. A non-privileged user can only log in at the same classification as the remote process.)
OUTGOING	A process shall succeed in requesting links to the specified node only if it is within the indicated classification range.
INCOMING	A process will receive incoming link requests from a remote process running on the specified node only if the remote process is running within the indicated classification range.
NOCLASSIFICATION	Overrides the default classification (unclassified) SEVMS uses for incoming connections that have no classification information. This includes connection requests from non-SEVMS nodes, as well as connections from unclassified processes running on SEVMS nodes. Because SEVMS cannot differentiate between the two cases, it is recommended that this keyword be used with non-SEVMS nodes only. A classification overridden by /NOCLASSIFICATION will be used in the check for /INCOMING and /REMOTE links.

/REMOVE

The /REMOVE qualifier enables a user to delete an unwanted record from the SEVMS\$LOGIN_CLASS.DAT database file.

This qualifier is added to the end of the SET CLASS/NODE command string; it uses the following format:

```
SET CLASS/NODE/LINK=link-type node-name/REMOVE
```

An example of using this qualifier with the SET CLASS/NODE command is provided in the examples section.

EXAMPLES

1 \$ SET CLASS/NODE/LINK=REMOTE TURBO/SECURITY=(LEVEL:SECRET)

A SET HOST from the node TURBO will only be allowed to login at SECRET.

2 \$ SET CLASS/NODE/LINK=NOCLASSIFICATION TURBO/
SECURITY=(LEVEL:SECRET)

Any link requests from node TURBO without classification information will be treated as they were from SECRET processes. Link requests from non-SEVMS systems and link requests from unclassified processes on SEVMS systems have no classification. This command would not be recommended if TURBO were an SEVMS system.

3 \$ SET CLASS/NODE/LINK=REMOTE TURBO/REMOVE

This command removes the classification (set in the above example) from node TURBO.

/REMOVE

The **/REMOVE** qualifier enables a user to delete an unwanted record from the SEVMS\$LOGIN_CLASS.DAT database file.

This qualifier is added to the end of the SET CLASS/SERVER command string; it uses the following format:

```
SET CLASS/SERVER server-name/REMOVE
```

```
SET CLASS/SERVER/PORT=port-name server-name/REMOVE
```

An example of using this qualifier with the SET CLASS/SERVER command is provided in the examples section.

EXAMPLES

1 \$ SET CLASS/SERVER FLOOR3/SECURITY=(LEVEL:SECRET)

The user changes the secrecy classification of all terminal ports on LAT server FLOOR3 to level SECRET.

2 \$ SET CLASS/SERVER/PORT=LC-1-9 FLOOR3/SECURITY=(LEVEL:SECRET)

The user changes the secrecy classification of the terminal port LC-1-9 on server FLOOR3 to level SECRET.

3 \$ SET CLASS/SERVER FLOOR3/REMOVE

This command removes the classification (set in the above example) for server FLOOR3.

SET CLASS/TERMINAL

SET CLASS/TERMINAL

The **SET CLASS/TERMINAL** command is used to create and modify log-in classification ranges for local interactive terminals.

When this command is used with the **/REMOVE** qualifier, it enables a user to delete an unwanted log-in classification range.

FORMAT

SET CLASS/TERMINAL */SECURITY=class-string*
terminal-name

restrictions

- The **/SECURITY** or **/INTEGRITY** qualifier is required.
- **SYSTEM** privilege is required.
- A user must have **WRITE** access to *SYS\$COMMON:[SYSEXE]SEVMS\$LOGIN_CLASS.DAT* to execute this command.
- Wildcards are not allowed in the command line.

PARAMETERS

terminal-name

Specifies the terminal to be associated with a classification. The *<terminal-name>* must have one of following formats:

Format	Device Type
<i><node-name>\$<device-name>[:]</i>	a specific device on a specific cluster node
<i><device-name>[:]</i>	a device on a system which is not part of a cluster

DESCRIPTION

The **SET CLASS/TERMINAL** command is used to create and modify log-in classification ranges for local interactive terminals in the *SEVMS\$LOGIN_CLASS.DAT* database file.

When this command is used with the **/REMOVE** qualifier, it enables a user to delete an unwanted log-in classification range from the database file.

While terminal devices are not cluster accessible, the *<node-name>\$<device-name>[:]* format is used to uniquely identify each device on the cluster in the shared cluster database. It is the same format that is returned by the **DVI\$ _DISPLAY_DEVNAM** item of the **\$GETDVI** system service, except that the colon is optional. The *<device-name>[:]* form is intended for use on systems which are not clustered and the

SCSNODE SYSGEN parameter is null. It will not match any terminal on a system where SCSNODE is defined.

If the device name specified in the terminal name is not one of the following device types: TT, TX, OP, or CS, **SET CLASS/TERMINAL** will return the following error:

```
"%SET-F-INVDEV, device is invalid for requested operation"
```

No check for existence of a node is made, since a node may not be a member of the cluster at the time the database is loaded. No check for existence of a device is made, since the database might be loaded before a controller is installed.

When **SET CLASS/TERMINAL** stores the terminal name in the database, it always includes the colon (:). The colon is optional in the command line.

QUALIFIERS

/SECRECY=class-string

See the description of this qualifier under the **SET** command.

/REMOVE

The **/REMOVE** qualifier enables a user to delete an unwanted record from the SEVMS\$LOGIN_CLASS.DAT database file.

This qualifier is added to the end of the **SET CLASS/TERMINAL** command string; it uses the following format:

```
SET CLASS/TERMINAL terminal-name/REMOVE
```

An example of using this qualifier with the **SET CLASS/TERMINAL** command is provided in the "Examples" section.

EXAMPLES

```
1 $ SET CLASS/TERMINAL/SECRECY=(LEVEL=SECRET) TURBO$TXA3:
```

Sets a classification for device TXA3 on node TURBO.

```
2 $ SET CLASS/TERMINAL/SECRECY=(LEVEL=SECRET) OPA0:
```

Sets a classification for device OPA0: on the system.

```
3 $ SET CLASS/TERMINAL TURBO$TXA3:/REMOVE
```

Removes the classification for device TTA3: on node TURBO (set in the above example).

SET TEMPLATE

The SET TEMPLATE command allows you to add, remove, or replace the association of an SEVMS print symbiont template with a specified secrecy level, category mask, printer, and printer width.

It also can be used to create a new, empty, template database (SEVMS\$SMB_HDRFRM.DAT) file.

FORMAT **SET TEMPLATE** [*template-name*]

restrictions

- Requires the SYSPRV privilege.

PARAMETERS ***template-name***

The name of the template for which an association is to be added or replaced. The *template-name* is required if the /ADD or /REPLACE qualifiers are specified. It is not used if the /REMOVE or /CREATE_DATABASE qualifiers are specified.

DESCRIPTION

The SET TEMPLATE command is used to control which templates the SEVMS print symbiont uses to print files. It does so by maintaining associations between template names and selection criteria in the symbiont database. The template is selected by the secrecy classification of the file, the device the file is being printed on and the width of the device.

SEVMS print symbiont templates, their creation, selection and use are discussed in the *VMS SES Security Manager's Guide*.

The command takes two types of qualifiers. The *operation* qualifiers specify what type of operation is to be performed; /ADD is the default. The *association* qualifiers indicate what the template is to be associated with; at least one association qualifier must be specified unless the /CREATE_DATABASE qualifier is specified.

**OPERATION
QUALIFIERS**

/ADD (default)

Specifies that a new association should be added for the template. If a template already has the same association specified, an error is returned.

/CREATE_DATABASE

Specifies a new, empty, template association database should be created.

/REMOVE

Specifies that an association should be removed from the database.

SET TEMPLATE

/REPLACE

Specifies that a new association should replace the existing association for the template. If no template had the same association, an error is returned.

ASSOCIATION QUALIFIERS

/CATEGORY_MASK=(*secrecy-category*[, . . .])

/CATEGORY_MASK=<ANY>

Specifies a secrecy category mask to associate with the template.

If this qualifier is not specified, or the special <ANY> keyword is used, the template will be associated with any secrecy category mask.

/LEVEL=secrecy-level

/LEVEL=<ANY>

Specifies a secrecy level to associate with the template.

If this qualifier is not specified, or the special <ANY> keyword is used, the template will be associated with any secrecy level.

/PRINTER=printer-name

/PRINTER=<ANY>

Specifies a printer to associate with the template. The printer-name can be either a physical device name (i.e. LPA0) or an SEVMS logical printer name. SET TEMPLATE does not check for the existence of the printer.

If this qualifier is not specified, or the special <ANY> keyword is used, the template will be associated with any printer.

An SEVMS logical printer name is established for the device ddcu: by defining the logical name SEVMS\$SMB_PRINTER_ddcu in the SYSTEM logical name table. The print symbiont will then use its definition rather than the physical device name to look for template associations. Refer to Chapter 7 of the *VMS SES Security Manager's Guide* for more information.

Note: The <ANY> keyword is provided for the qualifiers above to be consistent with the SHOW TEMPLATE command. Its use is optional, since the same effect on association can be obtained by omitting the qualifier.

/WIDTH=n

Specifies a printer line width to associate with the template.

If this qualifier is not specified, the template will be associated with a width of 0.

EXAMPLES

1 \$ SET TEMPLATE/CATEGORY=(1) CONFIDENTIAL_FORMAT

The print symbiont template named CONFIDENTIAL_FORMAT is associated with secrecy category 1.

SET TEMPLATE

2 \$ SET TEMPLATE/PRINTER=<ANY>/WIDTH=80 C80

This associates the print symbiont template named C80 with printer width 80. The /PRINTER=<ANY> qualifier is not needed since the default is to associate the template with any printer.

3 \$ SET TEMPLATE/LEVEL=SECRET/CATEGORY=(GREEN, YELLOW)/PRINTER=LINE -
_ \$ /WIDTH=132 EXAMPLE_111

This command associates the template named EXAMPLE_111 with secrecy level SECRET, category mask GREEN and YELLOW, SEVMS logical printer LINE, and printer width 132.

4 \$ SET TEMPLATE/CATEGORY=(GREEN, YELLOW) EXAMPLE_222

This command associates the template named EXAMPLE_222 with category mask GREEN and YELLOW.

5 \$ SET TEMPLATE/CATEGORY=(GREEN, YELLOW) /REMOVE

This command removes the association between the secrecy category mask of GREEN and YELLOW and the SEVMS print symbiont template associated with it (if any). This command does not affect any other print symbiont template except those with an exact match. (In this case, the template named EXAMPLE_222 is matched, and therefore the association is removed. Note that the association for the template named EXAMPLE_111 is unaffected.)

SHOW AUDIT

SHOW AUDIT

The SHOW AUDIT command displays the alarms that have been enabled with the SET AUDIT/SECURITY and SET AUDIT/INTEGRITY commands.

FORMAT **SHOW AUDIT /SECURITY**

restrictions

- Requires the SECURITY system privilege.
- The /SECURITY qualifier is required.

PARAMETERS *none*

DESCRIPTION

The SHOW AUDIT command requires the use of the /SECURITY qualifier for SEVMS.

The SHOW AUDIT/SECURITY command provides a display that identifies which security auditing features have been enabled with the SET AUDIT/SECURITY and SET AUDIT/INTEGRITY commands and the events that will be audited. There is not a SHOW AUDIT/INTEGRITY command; SHOW AUDIT/SECURITY is used to display both secrecy and integrity alarms.

This command is useful for checking which auditing features are enabled whenever you plan to add or delete features with a SET AUDIT/SECURITY or SET AUDIT/INTEGRITY command.

QUALIFIERS **/SECURITY**

The /SECURITY qualifier causes the set of auditing features that were enabled with the SET AUDIT/SECURITY and SET AUDIT/INTEGRITY commands, and the events they report, to be displayed. This qualifier is required.

EXAMPLES

1 \$ SHOW AUDIT/SECURITY
Mandatory access alarms currently disabled

In this example, mandatory access alarms are disabled.

2

\$ SHOW AUDIT/SECURITY

Mandatory access alarms currently enabled for:

FILE ACCESS SECURITY FAILURE LEVEL: CONFIDENTIAL, SECRET, VERY_SECRET

CATEGORY: RED

SUCCESS LEVEL: CONFIDENTIAL, SECRET

CATEGORY: RED, BLUE

This example displays classification-related audit information for FILE_ACCESS. (LABEL_BYPASS and PRINTED_FILE information would also be displayed in this example if they were enabled.)

SHOW CLASS

SHOW CLASS

The SHOW CLASS command allows you to view the classification associated with an object, process, LAT server, terminal port, or node.

FORMAT **SHOW CLASS** *name*

restrictions

- One of the listed qualifiers is required if the *name* is not a file. These qualifiers are mutually exclusive.
- The /PORT qualifier cannot be used without the /SERVER qualifier.

PARAMETERS *name*
Specifies the type of classification to be viewed.

DESCRIPTION This command enables the user to view the classification associated with an object, process, LAT server, terminal port, or node. The default of this command is an object which is a file; therefore, if a qualifier is not specified, a file object type is assumed for *name*. For all objects which are not files, the /OBJECT_TYPE qualifier is required. For any other type of *name*, a qualifier must be specified.

QUALIFIERS **/OBJECT_TYPE=type object-name**
Specifies the type of the object whose classification is being viewed.

By default, a file object type is assumed. If the object is not a file, this qualifier is required. The following keywords may be specified with /OBJECT_TYPE:

Type	Function
FILE	Specifies that the object type is a file or a directory file.
DEVICE	Specifies that the object type is a device.
SYSTEM_GLOBAL_SECTION	Specifies that the object type is a system global section.
GROUP_GLOBAL_SECTION	Specifies that the object type is a group global section.
QUEUE	Specifies that the object type is a queue.
LOGICAL_NAME_TABLE	Specifies that the object type is a logical name table.

/PROCESS [process-name]
Displays the classification of your process or any current subprocess. The default is the current process. Only processes in your own group can be

identified by name. To show the classification of a process outside your group you must use the **/IDENTIFICATION** qualifier.

Showing another process' classification requires:

- GROUP privilege to show other processes in the same group.
- BYPASS privilege to show processes more classified than your own.

/PROCESS/IDENTIFICATION=pid

Displays the classification of the process with the specified process ID. PID is the process identification number which you can get with the DCL SHOW SYSTEM command.

Showing another process' classification requires:

- GROUP privilege to show other processes in the same group.
- WORLD privilege to show processes outside your group.
- BYPASS privilege to show processes more classified than your own.

/SERVER server-name

This qualifier displays the classification of a LAT server. The server-name parameter specifies the name of the terminal server which is to have its classification displayed.

Using this qualifier to show the classification of a LAT server requires SYSPRV privilege.

If the **/SERVER** qualifier is used alone, it shows only the default classification (if any) for all ports on a specified server. To show the classification of individual (specific) ports, the **/PORT** qualifier must also be used.

The use of * is allowed; it is used to list all servers. The use of partial wildcarding (*) is allowed; it is used to specify a partial *server-name* with a wildcard (*) at the end.

/PORT=remote-port-name

This qualifier displays the classification of a port on a LAT server. The remote-port-name parameter specifies the name of a terminal port on a specified LAT server which is to have its classification displayed.

This qualifier can only be used in conjunction with the **/SERVER** qualifier. Using this qualifier to show the classification of a terminal port requires SYSPRV privilege.

The use of a full wildcard (*) is allowed; it is used to list all ports. However, the use of a full wildcard (*) with the **/PORT** qualifier is subject to the following restrictions: the *server-name* must be fully specified or the *server-name* must be a full wildcard (*). If the *server-name* is a wildcard (*), a fully specified *remote-port-name* is not allowed.

Partial wildcarding (*) is **not** allowed with the **/PORT** qualifier.

/NODE/LINK=(keyword) node-name

Displays the classification(s) of the logical link(s) on the specified node.

The **/LINK** qualifier specifies the type of logical link classification to be displayed. Using this command qualifier requires the SYSPRV privilege.

SHOW CLASS

The following keywords can be specified for the /LINK qualifier: REMOTE, INCOMING, OUTGOING, NOCLASSIFICATION, ALL.

The use of * is allowed for node names; it is used to list all nodes. The use of * is not allowed for link types in the /LINK qualifier (i.e. REMOTE, INCOMING, OUTGOING, NOCLASSIFICATION). Partial wildcarding (*) is allowed; it is used to specify a partial *node-name* with a wildcard (*) at the end.

Refer to the SET CLASS/NODE command for information about classifying nodes and a description of the /LINK keywords.

/TERMINAL terminal-name

The SHOW CLASS/TERMINAL command is used to display login classification ranges for local interactive terminals. A user must have READ access to SYS\$COMMON:[SYSEXEC]SEVMS\$LOGIN_CLASS.DAT to execute this command. By default, this means that the user must have SYSTEM privilege (SYSPRV). The format of this command is as follows:

SHOW CLASS/TERMINAL <terminal-name>

In the above format <terminal-name> must have one of following formats:

Format	Device types(s)
<node-name>\${<device-name> [:] ¹	a specific device on a specific cluster node
<device-name>[:] ¹	a device on a system which is not part of a cluster
<node-name>\${* ²	all terminal devices on the specified node
*	all terminal devices on all nodes

¹Partial wildcarding of the <device-name> is allowed (i.e. <partial-device-name>*).

²Partial wildcarding of the <node-name> is allowed (i.e. <partial-node-name>*).

As is shown in the above table, full and partial wildcarding of the *terminal-name* is allowed. Note that the wildcard must always be at the end of the partially specified *terminal-name*.

EXAMPLES

```
1 $ SHOW CLASS/OBJECT_TYPE=DEVICE DUA0
Object type: device,
Object name: DUA0, on 20-MAY-1989 20:17:51.78
Class: SECRECY=(LEVEL=UNCLASSIFIED,CATEGORY=(NONE))
```

This example shows the classification of the device DUA0.

```
2 $ SHOW CLASS/PROCESS
Object type: process,
Object name: SMITH, on 20-MAY-1989 20:17:53.17
Class: SECRECY=(LEVEL=UNCLASSIFIED,CATEGORY=(NONE))
```

This example shows the classification of the current process.

```

3 $ SHOW CLASS/SERVER/PORT=* *
Server/port classifications on 30-MAY-1989 12:53:39.39
Server: FLOOR2
Class: SECRECY=(LEVEL=(MINIMUM=0,MAXIMUM=3),CATEGORY=(123))
Server: FLOOR3
Class: SECRECY=(LEVEL=0,CATEGORY=(NONE))
Server/Port: FLOOR3/LC-1-9
Class: SECRECY=(LEVEL=0,CATEGORY=(NONE))

```

This example shows the classifications of all ports on all servers.

```

4 $ SHOW CLASS/SERVER *
Server classifications on 30-MAY-1989 12:54:39.59
Server: FLOOR2
Class: SECRECY=(LEVEL=(MINIMUM=0,MAXIMUM=3),CATEGORY=(123))
Server: FLOOR3
Class: SECRECY=(LEVEL=0,CATEGORY=(NONE))

```

This example shows the classification of all servers.

```

5 $ SHOW CLASS/SERVER/PORT=* FLOOR3
Server/port classifications on 30-MAY-1989 12:54:05.79
Server/Port: FLOOR3/LC-1-9
Class: SECRECY=(LEVEL=0,CATEGORY=(NONE))

```

This example shows the classifications of all ports on the specified server.

```

6 $ SHOW CLASS/SERVER FLOOR3
Server classifications on 30-MAY-1989 12:54:25.17
Server: FLOOR3
Class: SECRECY=(LEVEL=0,CATEGORY=(NONE))

```

This example shows the classification of a specified server.

```

7 $ SHOW CLASS/NODE/LINK=NOCLASSIFICATION TURBO
Node classifications on 21-SEP-1989 06:17:17.04
Link Type: NOCLASSIFICATION Node: TURBO
Class: SECRECY=(LEVEL=UNCLASSIFIED,CATEGORY=(NONE))

```

This example shows the classification that is associated with any link requests from node TURBO that do not have a classification.

```

8 $ SHOW CLASS/NODE/LINK=INCOMING TURBO
Node classifications on 21-SEP-1989 06:17:37.97
Link Type: INCOMING Node: TURBO
Class: SECRECY=(LEVEL=CONFIDENTIAL,CATEGORY=(NONE))

```

This example shows the classification that is required of incoming link requests on node TURBO.

SHOW CLASS

```
9 $ SHOW CLASS/NODE/LINK=ALL TURBO
Node classifications on 8-NOV-1989 14:00:44.84
Link Type : REMOTE Node : TURBO
Class: SECRECY=(LEVEL=2,CATEGORY=(NONE))
Link Type : INCOMING Node : TURBO
Class: SECRECY=(LEVEL=(MINIMUM=0,MAXIMUM=20),CATEGORY=(NONE))
Link Type : OUTGOING Node : TURBO
Class: SECRECY=(LEVEL=(MINIMUM=0,MAXIMUM=10),CATEGORY=(NONE))
Link Type : NOCLASSIFICATION Node : TURBO
Class: NO CLASSIFICATION FOUND
```

This example shows the classification of all links on node TURBO.

```
10 $ SHOW CLASS/TERMINAL *
Terminal classifications on 19-FEB-1990 13:31:31.25
Terminal: ANODE$TXA3:
Class: SECRECY=(LEVEL=SECRET,CATEGORY=(NONE))
Terminal: ZNODE$OPA0:
Class: SECRECY=(LEVEL=TOP_SECRET,CATEGORY=(A))
```

This example shows the login classification of all local interactive terminals.

```
11 $ SHOW CLASS/TERMINAL OP*
Terminal classifications on 22-MAY-1990 05:56:15.66
Terminal: OPAll:
Class: SECRECY=(LEVEL=SECRET,CATEGORY=(NONE))
Terminal: OPA8:
Class: SECRECY=(LEVEL=CONFIDENTIAL,CATEGORY=(NONE))
```

This example show the login classification of all terminals with a device name beginning with *OP*.

```
12 $ SHOW CLASS/NODE/LINK=ALL A*
Node classifications on 22-MAY-1990 06:08:58.54
Link Type : REMOTE Node : ABC1
Class: SECRECY=(LEVEL=CONFIDENTIAL,CATEGORY=(NONE))
Link Type : REMOTE Node : ABC2
Class: SECRECY=(LEVEL=CONFIDENTIAL,CATEGORY=(NONE))
Link Type : REMOTE Node : ABC3
Class: SECRECY=(LEVEL=CONFIDENTIAL,CATEGORY=(NONE))
Link Type : INCOMING Node : A*
Class: NO CLASSIFICATION FOUND
Link Type : OUTGOING Node : A*
Class: NO CLASSIFICATION FOUND
Link Type : NOCLASSIFICATION Node : A*
Class: NO CLASSIFICATION FOUND
```

This example shows the classification of all logical links on all nodes whose name begins with the letter A.

SHOW TEMPLATE

The SHOW TEMPLATE command displays the currently established associations between SEVMS print symbiont templates and secrecy levels, category masks, printers and printer widths.

FORMAT **SHOW TEMPLATE** *[template-name]*

restrictions

- Requires the SYSPRV privilege.

PARAMETERS ***template-name***

The name of the template for which an association is to be viewed.

DESCRIPTION

The SHOW TEMPLATE command displays the template associations used by the SEVMS print symbiont. Either some or all associations can be shown, as determined by the parameters and qualifiers specified, as follows:

- If no template name or qualifiers are specified, then all associations are shown.
- If only a template name is specified, then only associations for the template will be shown.
- If only qualifiers are specified, then only associations that match the qualifiers will be shown.
- If a template name and qualifiers are specified, then only associations that match the qualifiers for the template will be shown.

A special keyword, <ANY>, is provided to indicate that any value of a qualifier can be matched.

The creation, selection, and use of SEVMS print symbiont templates is discussed in the *VMS SES Security Manager's Guide*.

QUALIFIERS ***/CATEGORY_MASK=(secrecy-category[, . . .])***

/CATEGORY_MASK=<ANY>

Specifies a secrecy category mask that associations must match in order to be shown.

/LEVEL=secrecy-level

/LEVEL=<ANY>

Specifies a secrecy level that associations must match in order to be shown.

SHOW TEMPLATE

/PRINTER=printer-name

/PRINTER=<ANY>

Specifies a physical or SEVMS logical printer name that associations must match in order to be shown.

/WIDTH=n

Specifies a printer width that associations must match in order to be shown.

EXAMPLES

1 \$ SHOW TEMPLATE

```
Template associations in SYS$SYSROOT:[SYSLIB]SEVMS$SMB_HDRFRM.DAT;
at 2-AUG-1989 13:26:39.46
```

```
Printer: <ANY>, Width: 0, Level: CONFIDENTIAL,
  Category mask: <ANY>,
  Template: FOO
```

```
Printer: <ANY>, Width: 132, Level: <ANY>,
  Category mask: <ANY>,
  Template: BAR
```

```
Printer: <ANY>, Width: 132, Level: <ANY>,
  Category mask: <ANY>,
  Template: FOO
```

All template associations are shown.

2 \$ SHOW TEMPLATE FOO

```
Template associations in SYS$SYSROOT:[SYSLIB]SEVMS$SMB_HDRFRM.DAT;
at 2-AUG-1989 13:26:51.14
```

```
Printer: <ANY>, Width: 0, Level: CONFIDENTIAL,
  Category mask: <ANY>,
  Template: FOO
```

```
Printer: <ANY>, Width: 132, Level: <ANY>,
  Category mask: <ANY>,
  Template: FOO
```

This command shows all associations for print symbiont template FOO.

3 \$ SHOW TEMPLATE/LEVEL=<ANY>

```
Template associations in SYS$SYSROOT:[SYSLIB]SEVMS$SMB_HDRFRM.DAT;
at 2-AUG-1989 13:27:14.22
```

```
Printer: <ANY>, Width: 132, Level: <ANY>,
  Category mask: <ANY>,
  Template: BAR
```

SHOW TEMPLATE

Printer: <ANY>, Width: 132, Level: <ANY>,
Category mask: <ANY>,
Template: FOO

This command displays the templates that are not associated with a particular level.

```
4 $ SHOW TEMPLATE/WIDTH=132 FOO
```

Template associations in SYS\$SYSROOT:[SYSLIB]SEVMS\$SMB_HDRFRM.DAT;
at 2-AUG-1989 13:28:05.75

Printer: <ANY>, Width: 132, Level: <ANY>,
Category mask: <ANY>,
Template: FOO

This command displays only templates named FOO that were associated with a printer width of 132.

DIRECTORY

DIRECTORY

The DIRECTORY command provides a list of files, or information about a file or group of files.

FORMAT **DIRECTORY** *[file-spec[,....]]*

PARAMETERS *[file-spec[,...]]*
Specifies one or more files for which directory information is desired.

DESCRIPTION Usage of the DIRECTORY command under SEVMS is similar to its usage under standard VMS. However, under SEVMS, the classification of files is displayed if the /FULL or /SECURITY qualifiers are specified. Both of these qualifiers are available in VMS. Refer to the *VMS DCL Dictionary* for complete information on the DIRECTORY command.

NOTE: When the DIRECTORY command is issued for a directory on another network node, and the /FULL and/or the /SECURITY qualifiers are used, classification information is not displayed.

QUALIFIERS **/FULL**
Under SEVMS, the /FULL qualifier displays the classification of a file along with the other information normally displayed by the standard (VMS) version of the DIRECTORY command. If this qualifier is used when the DIRECTORY command is issued across the network, the classification will not be displayed.

/SECURITY
Under SEVMS, the /SECURITY qualifier displays the classification of a file along with the other security information normally displayed by the standard (VMS) version of the DIRECTORY command. If this qualifier is used when the DIRECTORY command is issued across the network, the classification will not be displayed.

EXAMPLES

1 \$ DIRECTORY/SECURITY [.DEMO]
 Directory \$DISK1:[J_SMITH.DEMO]

```

SECRET.DAT;1      [AGROUP, J_SMITH]      (RWED, RWED, RE, )
                SECRECY=(LEVEL=SECRET, CATEGORY=(NONE))
SECRET.MISC;1    [AGROUP, J_SMITH]      (RWED, RWED, RW, R)
                SECRECY=(LEVEL=SECRET, CATEGORY=(NONE))
SECRET_RED.MISC;1 [AGROUP, J_SMITH]      (RWED, RWED, RW, R)
                (ALARM_JOURNAL=SECURITY, ACCESS=READ+FAILURE)
                (IDENTIFIER=[123, 456], ACCESS=READ+WRITE+EXECUTE)
                (IDENTIFIER=[SYSTEM], ACCESS=DELETE)
                SECRECY=(LEVEL=SECRET, CATEGORY=(RED))
SECRET_RED.TXT;1 [SYSTEM]                (RWED, RWED, RE, )
                SECRECY=(LEVEL=SECRET, CATEGORY=(RED))
UNCLASS.MISC;1   [AGROUP, J_SMITH]      (RWED, RWED, RW, R)
                (IDENTIFIER=[AGROUP, JONES], ACCESS=NONE)
                SECRECY=(LEVEL=UNCLASSIFIED, CATEGORY=(NONE))
UNCLASS.TXT;1   [SYSTEM]                (RWED, RWED, RE, )
                SECRECY=(LEVEL=UNCLASSIFIED, CATEGORY=(RED, 63))

```

Total of 6 files.

This example displays security information, including the classification, of all files in directory [J_SMITH.DEMO].

2

```
$ DIRECTORY/FULL [.DEMO]UNCLASS.TXT
```

```
Directory $DISK1:[J_SMITH.DEMO]UNCLASS.TXT
```

```

UNCLASS.TXT;1      File ID: (869,20,0)
Size:              9/9      Owner:      [SYSTEM]
Created: 16-OCT-1989 13:23:10.86
Revised: 31-OCT-1989 08:13:44.84 (3)
Expires: <None specified>
Backup: <No backup recorded>
File organization: Sequential
File attributes:   Allocation: 9, Extend: 0, Global buffer count: 0, No version limit
Record format:    Variable length, maximum 79 bytes
Record attributes: Carriage return carriage control
RMS attributes:   None
Journaling enabled: None
File protection:  System:RWED, Owner:RWED, Group:RE, World:
Access Cntrl List: None
Classification:   SECRECY=(LEVEL=UNCLASSIFIED, CATEGORY=(RED, 63))

```

Total of 1 file, 9/9 blocks.

This example displays full information, which includes the classification, of the UNCLASS.TXT file in the directory [J_SMITH.DEMO].

/SECREC Y Qualifier Syntax

```

secrecy-qualifier := /SECREC Y=(class-string)
class-string := { LEVEL= level-range |
                  CATEGORY= category-range |
                  LEVEL= level-range,
                    CATEGORY= category-range }
level-range := { level |
                 (MAXIMUM:level) |
                 (MINIMUM:level, MAXIMUM:level) }
category-range := { category-list |
                   (MAXIMUM:(category-list)) |
                   (MINIMUM:(category-list),
                     MAXIMUM:(category-list)) }
category-list := { category |
                  (category [, . . . ]) }

```

Notes:

If not entered, minimum ranges default to 0 or none.

Colons (:) and equals signs (=) can be used interchangeably in the qualifier.

If MAXIMUM is specified for a single level object, it is ignored.

/INTEGRITY=class-string

Specifies one or more integrity levels and/or categories, or ranges of integrity levels and/or categories.

EXAMPLES

1 \$ INITIALIZE/SECREC Y=(LEVEL:2) DL0 USER

This example initializes the disk which is mounted on DL0 and labeled USER with the classification of secrecy level 2.

3

Programming Information

This chapter provides programming information about SEVMS. The topics included in this chapter are: an explanation of the SEVMS class block format, descriptions of the system service routines that are employed by SEVMS, and a description of SEVMS mandatory access control items and arguments which are used with VMS System Services. This chapter is divided into the following sections:


- Class Block Format
- System Services
- SEVMS Binary Audit Record Format

3.1 Class Block Formats

There are two possible formats for the SEVMS class block. One format (Type 0) is used when only secrecy categories of 64 or less are specified; the other format (Type 1) is used when secrecy categories above 64 are specified.


The first class block format (Type 0) has the original standard SEVMS format. This format is used for class blocks that do not contain secrecy categories greater than 64 and may (or may not) have integrity categories. The following figure, Figure 3-1, illustrates this class block.

Figure 3-1 Type 0 Class Block Format



The second class block (Type 1) uses a slightly modified form of the standard SEVMS class block format. This format is used for class blocks that do contain secrecy categories greater than 64 and do not have integrity categories. The following figure, Figure 3-2, illustrates this class block.

Figure 3-2 Type 1 Class Block Format



3.2 System Services

This section contains complete reference descriptions of the system service routines used by SEVMS. It also includes information about the mandatory access controls support for new items in VMS system services.

3.2.1 SEVMS Mandatory Access Control Items in VMS System Services

This section describes new items used by VMS system service routines which are related to mandatory access controls.

Refer to the *VMS System Services* manual for further information about the system services discussed in this section.

3.2.1.1 \$CHKPRO System Service

This system service can take the following items in its item list which are related to mandatory access controls:

- CHP\$_ACCLASS—accessors classification
- CHP\$_MINCLASS—minimum classification for the object
- CHP\$_MAXCLASS—maximum classification for the object

3.2.1.2 \$GETUAI System Service

This system service can take the following additional items in its item list which are related to SEVMS mandatory access controls:

- UAI\$_MIN_CLASS—minimum class block for UAF record
- UAI\$_MAX_CLASS—maximum class block for UAF record

3.2.1.3 \$CREPRC System Service

The \$CREPRC system service creates a subprocess or detached process on behalf of the calling process.

To support mandatory access controls, the argument *itmlst* can now be specified with the \$CREPRC system service. The *itmlst* argument allows the classification of a detached process to be specified.

The use of this argument is optional. If this argument is not specified, the detached process will have the same classification as that of the creating process. If this argument is specified, the creating process must have BYPASS privilege *and* either UPGRADE (to change integrity) or DOWNGRADE (to change secrecy) privilege, in order to specify a classification for the detached process which is different than its creator's classification.

The *itmlst* argument has been implemented as the 13th positional argument of the \$CREPRC system service.

ARGUMENT: *itmlst*

VMS Usage: item_list_2
type: longword (unsigned)
access: read only
mechanism: by reference

The *itmlst* argument is the address of an item list of descriptors used to specify the classification of a detached process.

For each item code, include an item descriptor and terminate the list with a longword containing the value of 0. For a description of *item_list_2*, refer to the section on data types in the *Introduction to VMS System Routines* manual.

The following item code is used with \$CREPRC.

Item Code	Description
SEVMS\$_PRC\$_ CLASS	The component address of a 20-byte classification block for a detached process. The component length must be 20.

RETURN VALUES:

The following status messages are returned if the classification of the detached process is different than that of the creating process and the creating process does not have the proper privileges.

SS\$_NOUPGRADE
 SS\$_NODOWNGRADE
 SS\$_NOBYPASS

3.2.1.4 \$QIO System Service — ACP-QIO Interface

The \$QIO system service can be used to request ACP operations by means of the ACP-QIO interface. One type of operation that can be requested by this interface is read/write attributes, to read or set the attributes of a file. The attributes to be read or set are specified by an attribute list.

One of the attributes that can be specified in the attribute list is the ATR\$C_CLASS_MASK. The specification of this attribute allows reading, or setting of, a file's classification. (Note: In order to set a file's classification, the file must be closed.)

The ACP-QIO interface, including the format of the attribute list, is described in detail in the *VMS I/O User's Reference Manual*. Note that the ATR\$C_CLASS_MASK is not documented in this manual as one of the attributes available. However, it is included in the system libraries that define these attributes (i.e. SYS\$LIBRARY:STARLET.REQ), and is supported by SEVMS.

3.2.2 SEVMS System Service Routines

This section describes the system service routines provided by SEVMS.

3.2.2.1 Introduction

SEVMS provides three system service routines that can be used to manipulate classification labels. These routines are listed in the following table. Refer to the routine description section of this chapter for complete information about these system service routines.

Service	Description
\$PARSE_CLASS	Converts ASCII text classification strings into a binary classification block.
\$FORMAT_CLASS	Converts an internal binary classification block into ASCII text classification strings.
\$CHANGE_CLASS	Gets and/or changes the classification of objects and processes.

3.2.2.2 Item Lists

All three system services take an item list argument whose items are identified by identical item codes, although a given system service may not use all the items. The type of item list used is an *item_list_3*. For a description of *item_list_3*, please refer to the section on data types in the *Introduction to VMS System Routines* manual. The following table, Table 3-1, describes the system service items used by SEVMS.

Table 3-1 SEVMS System Service Items

Item Code	Description
Input Items	
CLS\$_SECSTR	The address of a text string descriptor which points to an ASCII secrecy classification string. ^{1,5}
CLS\$_INTSTR	The address of a text string descriptor which points to an ASCII integrity classification string. ^{1,5}
CLS\$_CLSBLK	The address of a descriptor which points to a 20 byte binary classification block. ^{2,4}
CLS\$_MINCLSBLK	The address of a descriptor which points to a 20 byte binary classification block. ^{2,4} This block should contain the minimum classification for a ranged object. It has the same format as CLS\$_CLSBLK.
CLS\$_MAXCLSBLK	The address of a descriptor which points to a 20 byte binary classification block. ^{2,4} This block should contain the maximum classification for a ranged object. It has the same format as CLS\$_CLSBLK.
CLS\$_WIDTH	The address of a longword containing the maximum width, in characters, for the classification string produced by \$FORMAT_CLASS.
CLS\$_INDENT	The address of a longword containing the number of spaces to indent, with spaces, each line of the classification string produced by \$FORMAT_CLASS.
CLS\$_TRMDSC	The address of a string descriptor which points to a character string that is used to terminate each line of the classification string produced by \$FORMAT_CLASS.
Output Items	
CLS\$_SECSTR	The address of a descriptor which points to a buffer that will contain an ASCII secrecy classification string. ^{3,5}
CLS\$_INTSTR	The address of a descriptor which points to a buffer that will contain an ASCII integrity classification string. ^{3,5}
CLS\$_OLDCLSBLK	The address of a descriptor which points to a 20 byte binary classification block that will contain the old classification of the object. It has the same format as CLS\$_CLSBLK. ^{3,4}
CLS\$_OLDMINCLS	The address of a descriptor which points to a 20 byte binary classification block that will contain the old minimum classification of the object. It has the same format as CLS\$_CLSBLK. ^{3,4}

¹The item "buffer length" word should contain the length of the string or buffer, **NOT** the length of descriptor.

²The item "buffer length" word should contain 20, length of the classification block, **NOT** the length of the descriptor.

³The descriptor must be fixed length.

⁴Class blocks are defined in SYS\$LIBRARY:LIB.MLB (for MACRO, LIB.REQ or LIB.L32 for BLISS) in the \$CLSDEF macro.

⁵The maximum possible classification string length is 3072 bytes.

Table 3-1 (Cont.) SEVMS System Service Items

Item Code	Description
Output Items	
CLS\$_OLDMAXCLS	The address of a descriptor which points to a 20 byte binary classification block that will contain the old maximum classification of the object. It has the same format as CLS\$_CLSBLK. ^{3,4}

³The descriptor must be fixed length.

⁴Class blocks are defined in SYS\$LIBRARY:LIB.MLB (for MACRO, LIB.REQ or LIB.L32 for BLISS) in the \$CLSDEF macro.

The item codes are defined in the system macro library (\$CLSDEF).

\$PARSE_CLASS

The PARSE CLASS service parses the specified classification text string and translates it to the corresponding binary classification block.

FORMAT **SYSPARSE_CLASS** *itmlst*

RETURNS VMS Usage: **cond_value**
 type: **longword (unsigned)**
 access: **write only**
 mechanism: **by value**

Longword condition value. All system services return (by immediate value) a condition value in R0. Condition values that can be returned by this service are listed under "Return Values".

ARGUMENTS *itmlst*

VMS Usage: **item_list_3**
 type: **longword (unsigned)**
 access: **read only**
 mechanism: **by reference**

The *itmlst* argument is the address of an item list of descriptors used to specify the mandatory access control protection attributes of an object.

For each item code, include an item descriptor and terminate the list with a longword containing the value of 0. For a description of *item_list_3*, refer to the section on data types in the *Introduction to VMS System Routines* manual.

The following item codes are used with \$PARSE_CLASS. See Table 3-1 for information on the format of items.

Item Code	Use
CLS\$_SECSTR	The secrecy classification string to be parsed.
CLS\$_INTSTR	The integrity classification string to be parsed.
CLS\$_CLSBLK	The resulting classification block.
CLS\$_MINCLSBLK	The resulting minimum classification block.
CLS\$_MAXCLSBLK	The resulting maximum classification block.

The text strings for the secrecy and integrity class have a similar format. These text strings may specify the minimum and maximum levels and applicable categories (or compartments) for the secrecy or integrity class.

The rules used to parse these text strings are:

- The initial keyword (SECRECY or INTEGRITY) may be omitted. This is to allow the text string to be handled easily as a value for a qualifier or value for a command.

\$PARSE_CLASS

- The values specified for the levels and categories may be identifiers (for example, SECRET) or a simple numeric value (for example, 4).
- The level may be a single value or a list specifying minimum and maximum values.
- The categories may be a single value or a list of values or lists of minimum and maximum values.
- If the text string only supplies a single level, but the item list requests minimum and maximum classification blocks, the resulting minimum and maximum classification blocks are the same.
- If the text string specifies that minimum and maximum classification blocks are to be generated, but only a single output block is specified in the item list, the minimum classification block is returned.

DESCRIPTION

\$PARSE_CLASS converts a text string to the corresponding binary classification block.

- There is no way to determine from the output of \$PARSE_CLASS whether level or category was specified in the input string. In other words the output from (LEVEL=0), (CATEGORY=0), and (LEVEL=0,CATEGORY=0) all look the same.
- The output classification block always has both the secrecy and integrity fields filled in; the fields are just 0 if no classification of a given type was specified on input. In other words, the output is the same whether a secrecy of (LEVEL=0) is input, or whether no secrecy string is input.

RETURN VALUES

SS\$_NORMAL	The service successfully completed.
SS\$_ACCVIO	The input string or its descriptor cannot be read, the output buffer descriptor cannot be read, the output buffer cannot be written, or the output buffer is not large enough to contain the binary classification block.
SS\$_INVSECLASS	The input text string could not be correctly parsed to yield a binary secrecy class.
SS\$_NOSUCHID	An identifier used to represent a secrecy level, secrecy category, integrity level, or an integrity category did not exist in the rights database.

\$FORMAT_CLASS

The FORMAT CLASS service formats the specified binary classification block and converts it to the corresponding text string.

FORMAT **SY\$FORMAT_CLASS** *itmlst*

RETURNS VMS Usage: **cond_value**
 type: **longword (unsigned)**
 access: **write only**
 mechanism: **by value**

Longword condition value. All system services return (by immediate value) a condition value in R0. Condition values that can be returned by this service are listed under "Return Values".

ARGUMENTS *itmlst*

VMS Usage: **item_list_3**
type: **longword (unsigned)**
access: **read only**
mechanism: **by reference**

The *itmlst* argument is the address of an item list of descriptors used to describe the information to be formatted, as well as how the formatting is to be done.

For each item code, include an item descriptor and terminate the list with a longword containing the value of 0. For a description of *item_list_3*, please refer to the section on data types in the *Introduction to VMS System Routines* manual.

The following item codes are used with \$FORMAT_CLASS. See Table 3-1 for information on the format of items.

Item Code	Use
CLS\$_CLSBLK	The classification block to be formatted.
CLS\$_MINCLSBLK	The minimum classification block to be formatted. (It has the same format as CLS\$_CLSBLK.)
CLS\$_MAXCLSBLK	The maximum classification block to be formatted. (It has the same format as CLS\$_CLSBLK.)
CLS\$_WIDTH	The maximum width of the display. If this is zero or omitted, the output strings will be long strings with no line breaks.

\$FORMAT_CLASS

Item Code	Use
CLS\$_TRMDSC	A string of characters used to terminate each line (as determined by CLS\$_WIDTH) of the output strings. This is normally a <CR> <LF> sequence. If this is null or omitted, the output strings will be long strings with no line breaks.
CLS\$_INDENT	The number of spaces to prefix each line (as determined by CLS\$_WIDTH) of the output strings. This indents the output strings.
CLS\$_SECSTR	A text string representing the secrecy class.
CLS\$_INTSTR	A text string representing the integrity class.

Note: When a line width is specified and exceeded, multiple lines are created in the output buffer by appending the CLS\$_TRMDSC string to the end of each line segment. The beginning of each line segment is then indented the number of spaces specified by CLS\$_INDENT.

RETURN VALUES

SS\$_NORMAL	The service completed successfully.
SS\$_ACCVIO	One of the input buffers or its descriptor cannot be read, the output descriptors cannot be read, the output buffers cannot be written, or one of the output length words cannot be written.
SS\$_BUFFEROVF	The service successfully completed. One of the output buffers has overflowed and been truncated. This is indicated by a -1 as the length of the return string.

\$CHANGE_CLASS

itmlst

Address of a list of descriptors specifying the object's new access class (minimum and maximum) and pointers to where the object's original access class is to be saved.

The item list is used to specify the new access class for the specified object and buffers in which the previous access class may be placed.

The symbols are defined in the system marco library (\$CLSDEF). The values and meanings of these symbols are defined in the following table.

Item Code	Use
CLS\$_CLSBLK ¹	The binary classification block specifying the new classification.
CLS\$_MINCLSBLK ¹	The binary classification block specifying the new minimum classification. (It has the same format as CLS\$_CLSBLK.)
CLS\$_MAXCLSBLK ¹	The binary classification block specifying the new maximum classification. (It has the same format as CLS\$_CLSBLK.)
CLS\$_OLDCLSBLK	A classification block to contain the old classification. (It has the same format as CLS\$_CLSBLK.)
CLS\$_OLDMINCLS	A classification block to contain the old minimum classification. (It has the same format as CLS\$_CLSBLK.)
CLS\$_OLDMAXCLS	A classification block to contain the old maximum classification. (It has the same format as CLS\$_CLSBLK.)

¹If *objtyp* is specified as ACL\$_PROCESS, an SS\$_BADPARAM error occurs.

acmode

Address of a byte containing the access mode in which the arguments are validated. This is maximized with the mode of the caller.

DESCRIPTION

The \$CHANGE_CLASS system service is used either to observe or to modify the classification associated with any defined object. Process classifications can be observed, but cannot be modified.

For this service to succeed, the process must have the appropriate privileges (UPGRADE and/or DOWNGRADE, or BYPASS).

Observing a Classification

To use the \$CHANGE_CLASS system service to observe a classification, do not specify a new classification block in the *itmlst*. When a new classification is not specified, \$CHANGE_CLASS "gets" the classification of the specified object (acts as "GET_CLASS" system service).

To retrieve the classification of a process, remember the following things:

- You must use the CLS\$_OLDCLSBLK item code to obtain the process classification.

- If you are using the PROCESS ID to identify the process, the name descriptor must have the descriptor type of *unsigned longword* as the first word in the descriptor structure definition.

The process using \$CHANGE_CLASS to observe a classification must have READ access to the object. If just the old classification is desired, this is the only check that is performed.

Modifying a Classification

To use the \$CHANGE_CLASS system service to change the classification of an object, the process must have both READ and CONTROL access to the object.

To set a classification range for an object, the process must also have the SECURITY privilege. SEVMS requires the SECURITY privilege in order to restrict the ability to create a persistent channel.

If the process has the SECURITY privilege, the following things must be true for the reclassification to succeed:

- If only a new maximum classification is specified, it must dominate the old minimum classification.
- If only a new minimum classification is specified, it must be dominated by the old maximum.
- If the object has no valid classification and only a new minimum or maximum classification is specified, the classification which was not specified is set equal to the one that was specified.
- If both a new minimum and maximum classification are specified, the maximum classification must dominate the minimum classification.
- If any of the above checks fail, a SS\$_BADPARAM error is returned.
- If the minimum secrecy is not equal to the maximum secrecy, the DOWNGRADE privilege is required. An SS\$_NODOWNGRADE error is returned if the process does not have this privilege.
- If the minimum integrity is not equal to the maximum integrity, the UPGRADE privilege is required. An SS\$_NOUPGRADE error is returned if the process does not have this privilege.

If the process does not have the SECURITY privilege, it cannot set a classification range. In this case, the following things must be true for the reclassification to succeed:

- If only a new maximum classification is specified, it must equal the old minimum classification.
- If only a new minimum classification is specified, it must equal the old maximum classification.
- If both a new minimum and maximum classification are specified, they must be equal to each other.

\$CHANGE_CLASS

- If the object has no valid classification (the ORB\$V_CLASS_PROT flag is off), then the new minimum classification must equal the new maximum classification. If only one classification is specified, the other classification is set equal to it.
- If any of these checks fail, an SS\$_NOSECURITY error is returned.

In both of the above cases, if the process does not have the BYPASS privilege, the following things must be true for the reclassification to succeed:

- A process running at the same classification as the old minimum classification of the object, with the privileges of the current process, would have write access to the newly classified object. In other words, for a non-privileged process, the resultant minimum classification must dominate the object's old minimum classification; otherwise, DOWNGRADE (and/or UPGRADE) is required.
- If the check fails, an SS\$_NODOWNGRADE, or SS\$_NOUPGRADE, error is returned.

RETURN VALUES

SS\$_NORMAL	The service completed successfully.
SEVMS\$_NOVALIDCLASS	The service completed successfully, but the object did not have a valid class block prior to service execution.
SS\$_ACCVIO	The object type could not be read, the object name buffer or its descriptor could not be read, the classification block could not be read, the access mode byte could not be read, or the old classification block buffer or its descriptor could not be written.
SS\$_NOUPGRADE	An attempt was made to upgrade the access class of an object without the necessary UPGRADE or BYPASS privilege.
SS\$_NODOWNGRADE	An attempt was made to downgrade the access class of an object without the necessary DOWNGRADE or BYPASS privilege.
SS\$_BUFFEROVF	The service completed successfully. However the buffer specified to receive the old classification block overflowed and has been truncated.

3.3 SEVMS Binary Audit Record Format

The binary audit record format used by SEVMS is the same as that used by VMS; it is described in full in "Appendix A - Security Audit Message Format" of the *VMS Audit Analysis Utility Manual*.

In addition to the record types and packets described in the *VMS Audit Analysis Utility Manual*, SEVMS adds several new record types and packets. Information about these record types and packets is provided in the following subsections of this section.

3.3.1 SEVMS Audit Record Types and Subtypes

For SEVMS-unique audit records, the NSA\$W_FACILITY field in the audit header packet (described in *VMS Audit Analysis Utility Manual*) will contain the SEVMS facility code of 1062. When this field contains this SEVMS facility code, the record type and record subtype fields of the audit header packet will contain the SEVMS-unique information described in Table 3-2, which follows.

Table 3-2 SEVMS-unique Audit Record Types and Subtypes

Event Type	Event Class	Record Type	Record Subtype
Label bypass	success	1	1
Label bypass	fail	1	2
Printed file	success	1	4
Printed file	fail	1	3
Change class	success	2	1
Change class	fail	2	2

3.3.2 SEVMS Audit Data Packets

This section describes the audit data packets used by SEVMS.

The following table, Table 3-3, contains the values which are defined for SEVMS-unique packets. These packets are in addition to the packets described in "Section A.2 - Audit Data Packets" of the *VMS Audit Analysis Utility Manual*.

Table 3-3 SEVMS Audit Data Packets

Packet Type	Code	Meaning
OBJECT_MIN_CLASS	27	Minimum classification of an object. (Classification block) ⁶
OBJECT_MAX_CLASS	28	Maximum classification of an object. (Classification block) ⁶

⁶The format is described in "Appendix A" of the *VMS Audit Analysis Utility Manual*.

Table 3-3 (Cont.) SEVMS Audit Data Packets

Packet Type	Code	Meaning
NEW_MIN_CLASS	120	New minimum classification of an object (or attempted new minimum classification of an object). (Classification block) ⁶
NEW_MAX_CLASS	121	New maximum classification of an object. (or attempted new maximum classification of an object). (Classification block) ⁶
QUEMGR_JOB_NUMBER	123	Queue manager job number. (Longword)
SYMBIONT_PROCESS_ID	124	Symbiont process ID number. (Longword)

⁶The format is described in "Appendix A" of the *VMS Audit Analysis Utility Manual*.

A

SEVMS System Messages and Recovery Procedures

This section contains a listing of the errors, warnings, and informational messages which are issued by SEVMS. Included are a brief description of each message and the action to be taken in response to the message.

These system messages are unique to SEVMS; VMS system messages are described in the *VMS System Messages and Recovery Procedures Reference Volume*, which is a part of the VMS General User Subkit.

The format of SEVMS system messages is the same as that used for VMS system messages. For format information about system messages, refer to the *VMS System Messages and Recovery Procedures Reference Volume* which is a part of the VMS General User Subkit.

In the following descriptions of SEVMS system messages, a ? is used to represent the severity code which occurs in the message. In an actual system message, one of the following severity codes will appear in the message:

Severity Code	Meaning
E	error
F	fatal error
I	informational
S	success
W	warning

%SEVMS-?-BADFAOARG

Explanation: An error was encountered in an internal \$FAO call.

User Action: Submit an SEVMS SPR.

%SEVMS-?-BADFLARG

Explanation: The SEVMS Print Symbiont was unable to access the routine and/or shareable image specified in a .FORMAT_LINE template directive.

User Action: Check that the routine and shareable image names were specified correctly. Check that the routine entry point is a universal symbol.

%SEVMS-?-BADSYNTAX

Explanation: Insufficient or illegal arguments were specified in a SET TEMPLATE command.

SEVMS System Messages and Recovery Procedures

%SEVMS-?-BUFOVRFLO

Explanation: A line of a referenced template was greater than 512.

User Action: Reduce the length of the template line.

%SEVMS-?-CATOUTRNG

Explanation: Categories must be between 1 and 128. An out-of-range category number has been selected.

User Action: Use a valid category.

%SEVMS-?-CLASSPROTNEEDED

Explanation: The CLASS_PROT parameter must be on to perform this operation.

User Action: The dynamic SYSGEN parameter CLASS_PROT must be set to "1" to enable mandatory access controls.

%SEVMS-?-CLASSPROTOFF

Explanation: The CLASS_PROT parameter is off - classification will be ignored.

User Action: CLASS_PROT must be set to "1" to classify objects successfully.

%SEVMS-?-CLSHDRFRM

Explanation: An error was encountered closing SEVMS\$\$SMB_HDRFRM.DAT. Additional error messages (such as RMS errors) should also be displayed.

User Action: Correct the problem indicated by the additional error information.

%SEVMS-?-DEVCLS

Explanation: An error was encountered in an internal \$CHANGE_CLASS call.

User Action: Submit an SEVMS SPR.

%SEVMS-?-ERREADFRM

Explanation: An error was encountered accessing or parsing a record of a template in SEVMS\$\$SMB_LIB.TLB.

%SEVMS-?-ERREADHDR

Explanation: An error was encountered reading SEVMS\$\$SMB_HDRFRM.DAT. Additional error messages should be displayed.

User Action: Correct the problem indicated by the additional messages.

SEVMS System Messages and Recovery Procedures

%SEVMS-?-ERRONQUE

Explanation: An error was encountered setting up a print queue. Additional error messages should be displayed.

User Action: Correct the problem indicated by the additional messages.

%SEVMS-?-ERRWRTHDR

Explanation: An error was encountered writing SEVMS\$SMB_HDRFRM.DAT. Additional error messages should be displayed.

User Action: Correct the problem indicated by the additional messages.

%SEVMS-?-LEVOUTRNG

Explanation: Levels must be between 0 and 255. An out-of-range level number has been selected.

User Action: Use a valid level.

%SEVMS-?-LINTOOLNG

Explanation: A line of a referenced template was too long for the width of the printer.

User Action: Print the file on a wider printer or reformat the template so that shorter lines are generated.

%SEVMS-?-MININTGTRMAX

Explanation: The minimum integrity classification specified is greater than the maximum.

User Action: Specify a minimum integrity classification level that is no greater than the maximum.

%SEVMS-?-MINSECGRMAX

Explanation: The minimum security classification specified is greater than the maximum.

User Action: Specify a minimum security classification level that is no greater than the maximum.

%SEVMS-?-NOCLASSSUPPORT

Explanation: Classification not supported on the selected object.

User Action: NONE. The selected object (for example, an event flag cluster) cannot be classified with SET CLASS.

%SEVMS-?-NOFORMCAT

Explanation: There is no template associated with the specified security category.

%SEVMS-?-NOLABELS

Explanation: A file is being printed with no page headers and/or page trailers, using the /PASSALL switch.

SEVMS System Messages and Recovery Procedures

%SEVMS?-NOMODULE

Explanation: The template associated with a specific security category was not found in SEVMS\$SMB_LIB.TLB.

User Action: A template must be specified for the particular set of categories using the SET TEMPLATE command.

%SEVMS?-NOPASSALL

Explanation: An attempt was made to print a file using the /PASSALL qualifier on a queue where the qualifier was not allowed.

User Action: See the *VMS SES Security Manager's Guide* for more information on the print symbiont.

%SEVMS?-OPNHDRFRM

Explanation: An error was encountered opening SEVMS\$SMB_HDRFRM.DAT. Additional error messages should be displayed.

User Action: Correct the problem indicated by the additional messages.

%SEVMS?-OPNLIBRARY

Explanation: An error was encountered opening SEVMS\$SMB_LIB.TLB. Additional error messages should be displayed.

User Action: Correct the problem indicated by the additional messages.

%SEVMS?-PARSECLAS

Explanation: An error was encountered converting a class block to a text string.

User Action: Submit an SEVMS SPR.

%SEVMS?-PRINTTERM

Explanation: A print job was terminated due to error. Additional error messages should be displayed.

User Action: Correct the problem indicated by the additional messages.

%SEVMS?-SMALLHEADER

Explanation: The file header has no space allocated for classification.

User Action: Either:

- COPY the file to a new version (assuming CLASS_PROT is set to "1"),
or
- image backup and restore the entire disk with the SEVMS version of the BACKUP utility.

%SEVMS-?-TOOMANVAR

Explanation: More .PAGE directives were specified in a template definition than is currently supported.

User Action: Reduce the number of .PAGE directives used in the template. Report this in an SPR so that the number may be increased in future versions of SEVMS.

%SEVMS-?-USRFLERR

Explanation: The customer-supplied formatting routine returned an error when called by a .FORMAT_LINE template directive.

User Action: Take action appropriate for the specific error returned by the customer-supplied formatting routine.

Glossary

This glossary contains definitions of terms used in VMS SES documentation. Included are terms which pertain to SEVMS, or which pertain to computer security in general.

To provide consistency and avoid confusion in VMS SES documentation, many of the definitions of terms included in this glossary have been taken from the *Department of Defense Trusted Computer System Evaluation Criteria*, DoD 5200.28-STD.

Some terms used in VMS SES documentation are described in VMS documentation, in the VMS General User Subkit, *General User Volume - Glossary*, and are not repeated in this glossary.

access: A specific type of interaction that takes place between a subject and an object that permits the flow of information from one to the other.

ACL: See *Access Control List*.

access control list: A list that defines the types of access to be granted or denied to users of an object - used for discretionary access control. Access control lists can be created for objects such as files, VMS devices, and mailboxes. Each access control list consists of one or more entries known as access control list entries.

access controls: See *mandatory access controls* and *discretionary access controls*.

access rights block (ARB): A VMS data structure associated with a process containing mandatory and discretionary access control information, as well as information about privileges.

alarm: See *security alarm*.

ARB: See *access rights block*.

auditing: See *security auditing*.

audit archive file: An SEVMS RMS sequential file with a binary record format in which audit records are stored for later analysis.

breakin attempt: An effort made by an unauthorized source to gain access to a system.

categories: See *secrecy categories*.

classification: The combination of secrecy and integrity levels and categories.

classification block (CL\$): The binary representation of a classification.

Glossary

classification label: A piece of information that represents the security level of an object. It describes the classification (or sensitivity) of the data in the object. Classification labels are used by the Trusted Computing Base as the basis for mandatory access control decisions.

clearance: See *security clearance*.

data: Information with a specific physical representation.

discretionary controls: Security controls that are applied at the user's option; the system does not require their use. Access control lists (ACLs) are an example of such optional security features.

discretionary access control: A means of restricting access to an object based on the identity of subjects and/or groups to which they belong. The controls are discretionary in the sense that a subject with a certain access permission is capable of passing that permission (perhaps indirectly) on to any other subject (unless restrained by mandatory access control).

dominate: Security level S1 is said to dominate security level S2 if the hierarchical classification of S1 is greater than or equal to that of S2 and the non-hierarchical categories of S1 include all those of S2 as a subset.

Integrity: Preservation of the trustworthiness of the data contained in a classified object. (i.e. An assurance that data has not been altered.)

Integrity level: One of two factors which define the integrity of an object. SEVMS supports up to 255 integrity levels.

Integrity category: One of two factors which define the integrity of an object. SEVMS supports up to 64 integrity categories.

label: See *classification label*.

level: See *integrity levels*. See also *secrecy levels*.

mandatory controls: See *mandatory access controls*.

mandatory access controls: A method of restricting access to an object based upon the sensitivity of the information contained in the object (determined by the object's classification label) and the authorization of a subject to access classified information (determined by the subject's classification).

multi-level device: A device that is used in a manner that permits it to simultaneously process data of two or more security levels without risk of compromise.

non-discretionary access controls: See *mandatory access controls*.

object: A system resource such as a file, device, or directory. A passive entity that contains or receives information. Access to an object implies access to the information it contains.

object rights block (ORB): A VMS data structure associated with an object containing access control information.

ORB: See *object rights block*.

read: A fundamental operation that results only in the flow of information from an object to a subject.

read-down: The subject can read an object with a lower classification than itself.

read-up: The subject can read an object with a higher classification than itself.

read access: Permission to read information.

secrecy: Preservation of the confidentiality of the data contained in a classified object.

secrecy category: One of two factors which define the secrecy of an object. SEVMS can have up to 128 secrecy categories. Secrecy categories are non-hierarchical.

secrecy level: One of two factors which define the secrecy of an object. SEVMS can have from 0 to 255 secrecy levels. Secrecy levels are hierarchical.

security alarm: A message sent to specified operator terminals which are enabled to receive security alarms. Security alarms are triggered by the occurrence of events previously designated by the security or system manager.

security auditing: The monitoring and recording of specified events occurring on the system. Examples of events which can be monitored are login failures, privileged and unprivileged access to system objects, changes to the user authorization file, etc.

breach: A break in system security that results in admittance of a person or program to an object.

Security Enhancement Service (SES): See *VMS Security Enhancement Service*.

security manager: The person responsible for the enforcement of security policies, procedures, and practices on a computer system. SEVMS security management tasks are sometimes performed by the system manager.

security policy: A set of rules and practices that define and regulate how an organization manages, protects, and distributes sensitive information.

sensitivity label: See *classification*.

SES: See *VMS Security Enhancement Service*.

SEVMS: Licensed software component of VMS Security Enhancement Service.

single-level device: A device that is used to process data of a single security level at any one time. In SEVMS, it is a device assigned a single classification rather than a classification range.

subject: An active entity, generally in the form of a person, process, or device that causes information to flow among objects, or changes the system state.

Glossary

system manager: The person responsible for the policies, procedures, and daily operation of a computer system. VMS system management tasks are sometimes performed by more than one person and might also include responsibilities for cluster management and security management.

Trusted Computing Base (TCB): The totality of protection mechanisms within a computer system - including hardware, firmware, and software - the combination of which is responsible for enforcing a security policy. A TCB consists of one or more components that together enforce a unified security policy over a product or system. The ability of a TCB to correctly enforce a security policy depends solely upon the mechanisms within the TCB and on the correct input by system administrative personnel of parameter (such as a user's clearance) related to the security policy.

VMS Security Enhancement Service (VMS SES): A software security consulting product. Provides a means of devising a system-wide security policy using mandatory access controls. Combines consulting services with packaged application software and documentation.

VMS SES: See *VMS Security Enhancement Service*

write-down: The subject can write to an object with a lower classification than itself.

write-up: The subject can write to an object with a higher classification than itself.

write access: Permission to write to an object.

Index

A

Access
definition of • Glossary–1

Access Control List
see ACL
definition of • Glossary–1

Access controls
definition of • Glossary–1
relationship of mandatory and discretionary controls • 1–6

Access rights block (ARB)
definition of • Glossary–1

Access rules
description of • 1–4
effect of privileges • 1–5

ACL
as a part of discretionary access controls • 1–1
definition of • Glossary–1

ACL\$C_DEVICE object type • 3–11

ACL\$C_FILE object type • 3–11

ACL\$C_GROUP_GLOBAL_SECTION object type • 3–11

ACL\$C_LOGICAL_NAME_TABLE object type • 3–11

ACL\$C_SYSTEM_GLOBAL_SECTION object type • 3–11

Add qualifier • 2–23

Alarm
definition of • Glossary–1

ALARM qualifier
with SET AUDIT command • 2–9

ALL keyword
of ANALYZE/AUDIT/EVENT_TYPE command • 2–2

ANALYZE/AUDIT command • 2–2 to 2–4
examples of use • 2–3
qualifiers • 2–3
SEVMS qualifiers • 2–3

Analyzing an audit • 2–2

ARB
definition of • Glossary–1

Audit
using SET AUDIT command • 2–9

Audit archive file
analyzing • 2–2
definition of • Glossary–1

Auditing
definition of • Glossary–1
using SET AUDIT command • 2–5
using SET command • 2–5

Audit record format • 3–15

Audit records
analyzing • 2–2

Audit record types and subtypes
chart of • 3–15

B

Binary audit record
data packets • 3–15

Binary audit record format • 3–15

Binary classification block • 3–7

Breakin attempt
definition of • Glossary–1

Bypassing page labels
auditing of • 2–9

BYPASS privilege
affect on mandatory access controls • 1–5

C

Categories
definition of • Glossary–1

Category • 2–5

Category mask • 2–23

CATEGORY qualifier
with SET AUDIT command • 2–9

CATEGORY_MASK qualifier • 2–24
of SHOW TEMPLATE command • 2–33

\$CHANGE_ACL item code • 3–11

\$CHANGE_CLASS
description of • 3–12

CHANGE_CLASS keyword
of ANALYZE/AUDIT/EVENT_TYPE command • 2–2

\$CHANGE_CLASS system service routine • 3–4, 3–11
return values • 3–14

\$CHKPRO system service • 3–2

Class

Index

Class (Cont.)
 using SET CLASS command • 2-5

Class block format
 description of • 3-1

Classification
 advantages of • 1-1
 definition of • Glossary-1
 determining for directories • 1-9
 determining for files • 1-9
 of directories • 1-8, 1-11
 example of • 1-11
 of files • 1-8, 1-11
 example of • 1-11
 of process at log-in • 1-7
 of sessions • 1-8
 propagation of • 1-8
 purpose of • 1-1
 range • 2-5
 using SECRECY qualifier • 1-11
 using SET command • 2-5

Classification block
 definition of • Glossary-1

Classification change
 auditing of • 2-9

Classification label
 definition of • Glossary-1
 description of • 1-4
 example of assignment • 1-4
 introduction to • 1-2
 list of objects and subjects • 1-4

Classification range
 description of • 1-7

CLASS qualifier
 with SET DEVICE command • 2-20

Clearance
 definition of • Glossary-2

CLS\$_CLSBLK item code • 3-7, 3-9, 3-12

CLS\$_INDENT item code • 3-10

CLS\$_INTSTR item code • 3-7, 3-10

CLS\$_MAXCLSBLK item code • 3-7, 3-9, 3-12

CLS\$_MINCLSBLK item code • 3-7, 3-9, 3-12

CLS\$_SECSTR item code • 3-7, 3-10

CLS\$_TRMDSC item code • 3-10

CLS\$_WIDTH item code • 3-9

Command
 see DCL command

Command syntax
 of SEVMS commands • viii
 of VMS commands • viii

Conventions
 SEVMS • viii

Conventions (Cont.)
 VMS • viii
 CREATE_DATABASE qualifier • 2-23
 \$CREPRC system service • 3-3

D

DAC
 see Discretionary Access Controls

Data
 definition of • Glossary-2

Data packet
 of SEVMS audit record • 3-15

DCL command
 DIRECTORY command • 2-36
 introduction to • 2-1
 reference information • 2-1 to 2-39
 /REMOVE qualifier for SET CLASS command •
 2-14, 2-17, 2-19
 SET AUDIT command • 2-8
 SET CLASS command • 2-11
 SET CLASS/NODE command • 2-13, 2-14
 SET CLASS/SERVER command • 2-16
 SET CLASS/SERVER/PORT/SECRECY
 command • 2-16
 SET CLASS/TERMINAL command • 2-18, 2-19
 SET command • 2-5
 SET DEVICE/CLASS command • 2-20
 SET DIRECTORY/CLASS command • 2-21
 SET FILE/CLASS command • 2-22
 SET TEMPLATE command • 2-23
 SHOW AUDIT command • 2-26
 SHOW CLASS command • 2-28
 SHOW TEMPLATE command • 2-33

DCL Command
 ANALYZE/AUDIT command • 2-2

DECwindows session
 logging into • 1-7

Device
 classification of • 1-4
 using SET DEVICE command • 2-5

DIGITAL consultant
 services provided by • v

Directory
 classification of • 1-8, 1-11
 determining classification of • 1-9
 determining structure of • 1-9
 example of classification • 1-11
 example of organization • 1-9
 hierarchy of • 1-9

Directory (Cont.)
 organization of • 1–9
 using SET DIRECTORY command • 2–5

DIRECTORY command
 description of • 2–36
 examples of • 2–36
 qualifiers • 2–36

DISABLE qualifier
 with SET AUDIT command • 2–8, 2–9

Discretionary access control
 definition of • Glossary–2

Discretionary access controls
 description of • 1–6
 list of access types • 1–6
 relation to mandatory access controls • 1–6
 use of ACLs • 1–1

Discretionary controls
 definition of • Glossary–2

Documentation
 associated SEVMS manuals • vi
 associated VMS manuals • vi, vii
 description of • v
 relationship of VMS and SEVMS manuals • vii

Document structure • v

Dominate
 definition of • viii, Glossary–2
 description of • 1–3
 in relation to mandatory access controls • 1–5

DOWNGRADE privilege • 2–6
 affect on mandatory access controls • 1–5
 with SET AUDIT command • 2–9

E

ENABLE qualifier
 with SET AUDIT command • 2–8, 2–9

Error messages • A–1

EVENT_TYPE qualifier
 description of • 2–2, 2–3
 keywords of • 2–2, 2–3
 use with FACILITY=SEVMS qualifier • 2–2

F

FACILITY=SEVMS qualifier • 2–2

File
 classification of • 1–8, 1–11
 determining classification of • 1–9

File (Cont.)
 example of classification • 1–11
 organization in directory • 1–9
 using SET FILE command • 2–5

File access
 auditing of • 2–9

FILES-11 volume
 initialization of • 2–38

Formatted text string • 3–10

\$FORMAT_CLASS system service routine • 3–4, 3–9
 arguments • 3–9, 3–11
 return values • 3–10

FULL qualifier
 of DIRECTORY command • 2–36

G

\$GETUAI system service • 3–2
 \$GET_CLASS system service • 3–12

I

ID (of a process)
 see PID

INITIALIZE command
 description of • 2–38
 examples of • 2–39
 qualifiers • 2–38

Integrity
 caution about use of • 1–3
 definition of • Glossary–2
 using SET command • 2–6

Integrity category
 definition of • Glossary–2
 description of • 1–3
 introduction to • 1–2

Integrity level
 definition of • Glossary–2
 description of • 1–3
 introduction to • 1–2

INTEGRITY qualifier
 description of • 2–6
 of INITIALIZE command • 2–39

Intended audience • v

Item
 descriptor • 3–7

Item lists
 of SEVMS system service routines • 3–4

Index

Items

related to mandatory access controls • 3-2

L

Label

see Classification label
definition of • Glossary-2

LABEL_BYPASS keyword
of **ANALYZE/AUDIT/EVENT_TYPE** command •
2-2

Level • 2-5
definition of • Glossary-2

LEVEL qualifier • 2-24
of **SHOW TEMPLATE** command • 2-33
with **SET AUDIT** command • 2-9

Licensed software
of VMS Security Enhancement Service • v

LINK qualifier
of **SET CLASS/NODE** command • 2-14

Logical printer name • 2-24

Login

classification of session • 1-8
default classification (at) • 1-7
errors • 1-7
example of • 1-7
in classified environment • 1-7
to DECwindows session • 1-7

M

MAC

see Mandatory access controls

Mandatory access control item • 3-2

Mandatory access controls

circumvention of • 1-5
definition of • 1-1, Glossary-2
description of • 1-2
description of rules • 1-4
enforcement of • 1-5
implementation of read access • 1-6
implementation of write access • 1-6
relation to discretionary access controls • 1-6
table of rules • 1-5

Mandatory access types
description of • 1-6

Mandatory controls
definition of • Glossary-2

Modifying classification

use of **\$CHANGE_CLASS** • 3-12

Multi-level device

definition of • Glossary-2

N

NODE qualifier

of **SHOW CLASS** command • 2-29

Non-discretionary access
definition of • 1-1

Non-discretionary access controls
definition of • Glossary-2

O

Object • 2-28

definition of • Glossary-2
introduction to • 1-2
list of • 1-4

OBJECT qualifier

of **SHOW CLASS** command • 2-28

Object rights block (ORB)
definition of • Glossary-2

Object type
for **SHOW CLASS** command • 2-28

Observing classification
use of **\$CHANGE_CLASS** • 3-12

Operator
definition of • viii

ORB
definition of • Glossary-2

ORB\$V_CLASS_PROT flag • 3-14

P

Packet type values

chart of • 3-15

\$PARSE_CLASS system service routine • 3-4, 3-7
arguments • 3-7
return values • 3-8

PID

obtaining with **SHOW CLASS** command • 2-29

PRINTED_FILE keyword
of **ANALYZE/AUDIT/EVENT_TYPE** command •
2-2

Printer
 association with templates • 2-24
 Printer name width • 2-23
 PRINTER qualifier
 of SHOW TEMPLATE command • 2-33
 Printing files
 auditing of • 2-9
 Print job
 using SET command • 2-5
 PRINT keyword
 of ANALYZE/AUDIT/EVENT_TYPE command • 2-3
 Print symbiont • 2-23
 Privilege
 DOWNGRADE • 2-6, 2-9
 SECURITY • 2-6
 SECURITY privilege • 2-8, 2-26
 SYSPRV privilege • 2-23
 UPGRADE • 2-9
 UPGRADE privilege • 2-6
 used to circumvent mandatory access controls • 1-5
 PRIVILEGES_USED keyword
 of ANALYZE/AUDIT/SELECT command • 2-3
 Process ID
 see PID
 PROCESS/IDENTIFICATION qualifier
 of SHOW CLASS command • 2-29
 PROCESS qualifier
 of SHOW CLASS command • 2-28
 Programming information • 3-1 to 3-16
 Propagation of classification • 1-8

Q

QUEMGR_JOB_NUMBER keyword
 of ANALYZE/AUDIT/SELECT command • 2-3

R

Range
 see Classification range
 Read
 definition of • Glossary-3
 Read access
 definition of • Glossary-3
 implementation of • 1-6

READALL privilege
 affect on mandatory access controls • 1-5
 Read-down
 definition of • Glossary-3
 description of • 1-5
 READ ONLY privilege • 1-5
 Read-up
 definition of • Glossary-3
 Read/write equal
 description of • 1-5
 READ/WRITE privilege • 1-5
 Recovery procedures • A-1
 REMOVE qualifier • 2-23
 REPLACE qualifier • 2-24

S

Scalar
 definition of • viii
 Secrecy
 definition of • Glossary-3
 SECRECY=class-string qualifier • 2-5
 description of • 2-5
 Secrecy category
 definition of • Glossary-3
 description of • 1-3
 introduction to • 1-2
 Secrecy level
 definition of • Glossary-3
 description of • 1-3
 introduction to • 1-2
 SECRECY qualifier • 1-7, 2-5, 2-26
 description of • 2-5
 of INITIALIZE command • 2-38
 with SET AUDIT command • 2-8
 with SET CLASS command • 2-11
 with SET CLASS/NODE command • 2-14
 with SET CLASS/SERVER command • 2-16
 with SET CLASS/TERMINAL command • 2-19
 with SET DEVICE command • 2-20
 with SET DIRECTORY command • 2-21
 with SET FILE command • 2-22
 with SHOW AUDIT command • 2-26
 Security alarm
 definition of • Glossary-3
 Security auditing
 definition of • Glossary-3
 security breach
 definition of • Glossary-3

Index

- Security category
 - conventions used • viii
- Security Enhancement Service • v
 - see also VMS SES
 - definition of • Glossary-3
- Security features
 - description of • 1-2
- Security level
 - conventions used • viii
- Security manager
 - definition of • Glossary-3
 - description of duties • 1-1
 - duties of • 1-8
 - use of this manual • v
- Security policy
 - definition of • Glossary-3
- SECURITY privilege • 2-6, 2-26
 - affect on mandatory access controls • 1-5
 - use with SET AUDIT command • 2-8
- SECURITY qualifier • 2-36
 - of DIRECTORY command • 2-36
- SELECT qualifier
 - description of • 2-3
 - keywords of • 2-3
 - of ANALYZE/AUDIT command • 2-3
- Sensitivity label
 - definition of • Glossary-3
- SERVER/PORT qualifier
 - of SHOW CLASS command • 2-29
- SERVER qualifier
 - of SHOW CLASS command • 2-29
- SES
 - see VMS SES
 - definition of • Glossary-3
- SES Documentation
 - description of • v
- Session classification
 - displaying • 1-8
- Set
 - definition of • viii
- SET AUDIT/ALARM command • 2-9
- SET AUDIT command • 2-8
 - examples of use • 2-10
 - introduction to • 2-5
 - qualifiers • 2-8
- SET AUDIT/SECURITY command • 2-8
- SET/CLASS command
 - description of • 2-11
 - example of use • 1-11
 - introduction to • 2-5
 - SECURITY qualifier • 2-11
- SET CLASS/NODE command
 - description of • 2-13
 - description of qualifiers • 2-14
 - examples of use • 2-14
 - /LINK qualifier • 2-14
- SET CLASS/SECURITY command
 - example of use • 2-11
- SET CLASS/SERVER command
 - description of • 2-16
 - description of /PORT qualifier • 2-16
- SET CLASS/SERVER/SECURITY command
 - example of use • 2-17
- SET CLASS/TERMINAL command
 - description of • 2-18
 - description of qualifiers • 2-19
 - examples of use • 2-19
- SET command
 - CLASS/NODE option • 2-13
 - CLASS/SERVER option • 2-16
 - CLASS/TERMINAL option • 2-18
 - DEVICE/CLASS option • 2-20
 - DIRECTORY/CLASS option • 2-21
 - example of use • 2-7
 - FILE/CLASS option • 2-22
 - INTEGRITY qualifier • 2-6
 - introduction to • 2-5
 - qualifiers • 2-5
- SET DEVICE/CLASS command
 - description of • 2-20
 - example of use • 2-20
- SET DEVICE command
 - introduction to • 2-5
- SET DIRECTORY/CLASS command
 - description of • 2-21
 - example of • 2-21
 - example of use • 1-11
- SET DIRECTORY/CLASS/SECURITY command
 - example of • 2-22
- SET DIRECTORY command
 - introduction to • 2-5
- SET FILE/CLASS command
 - description of • 2-22
- SET FILE command
 - introduction to • 2-5
- SET TEMPLATE command
 - introduction to • 2-5
- SET TEMPLATE Command
 - description of • 2-23
 - example of use • 2-24
 - qualifiers • 2-23
- SEVMS

- SEVMS (Cont.)
 - advantages of • 1–1
 - conventions of • viii
 - definition of • v, Glossary–3
 - description of • 1–1
 - intent of • 1–1
 - security techniques • 1–2
- SEVMS\$\$SMB_HDRFRM.DAT database
 - creation of • 2–23
- %SEVMS-?-BADFAOARG message • A–1
- %SEVMS-?-BADFLARG message • A–1
- %SEVMS-?-BADSYNTAX message • A–1
- %SEVMS-?-BUFOVRFLO message • A–1
- %SEVMS-?-CATOUTRNG message • A–2
- %SEVMS-?-CLASSPROTNEEDED message • A–2
- %SEVMS-?-CLASSPROTOFF message • A–2
- %SEVMS-?-CLSHDRFRM message • A–2
- %SEVMS-?-DEVCLS message • A–2
- %SEVMS-?-ERREADFRM message • A–2
- %SEVMS-?-ERREADHDR message • A–2
- %SEVMS-?-ERRONQUE message • A–2
- %SEVMS-?-ERRWRTHDR message • A–3
- %SEVMS-?-LEVOUTRNG message • A–3
- %SEVMS-?-LINTOOLNG message • A–3
- %SEVMS-?-MININTGTRMAX message • A–3
- %SEVMS-?-MINSECGRMAX message • A–3
- %SEVMS-?-NOCLASSSUPPORT message • A–3
- %SEVMS-?-NOFORMCAT message • A–3
- %SEVMS-?-NOLABELS message • A–3
- %SEVMS-?-NOMODULE message • A–3
- %SEVMS-?-NOPASSALL message • A–4
- %SEVMS-?-OPNHDRFRM message • A–4
- %SEVMS-?-OPNLIBRARY message • A–4
- %SEVMS-?-PARSECLAS message • A–4
- %SEVMS-?-PRINTTERM message • A–4
- %SEVMS-?-SMALLHEADER message • A–4
- %SEVMS-?-TOOMANVAR message • A–4
- %SEVMS-?-USRFLERR message • A–5
- SEVMS binary audit record format • 3–15
- SEVMS DCL commands
 - see DCL commands
- SEVMS documentation
 - associated manuals • vi
- SHOW AUDIT command
 - description of • 2–26
 - qualifiers • 2–26
- SHOW AUDIT/SECRECY command • 2–9
 - examples of • 2–26
- SHOW CLASS command
 - description of • 2–28
 - examples of • 2–29
- SHOW CLASS command (Cont.)
 - qualifiers • 2–28
- SHOW CLASS/PROCESS command
 - example of use • 1–8
- SHOW TEMPLATE command
 - description of • 2–33
 - examples of • 2–34
 - qualifiers • 2–33
- Single-level device
 - definition of • Glossary–3
- SQn qualifier
 - description of • 2–6
- SS\$_ACCVIO message • 3–8, 3–10, 3–14
- SS\$_BADPARAM message • 3–13
- SS\$_BUFFEROVF message • 3–10, 3–14
- SS\$_INVSECLASS message • 3–8
- SS\$_NODOWNGRADE message • 3–13, 3–14
- SS\$_NORMAL message • 3–8, 3–10, 3–14
- SS\$_NOSECURITY message • 3–14
- SS\$_NOSUCHID message • 3–8
- SS\$_NOUPGRADE message • 3–13, 3–14
- Subdirectory
 - hierarchy of • 1–9
 - organization of • 1–9
- Subject
 - definition of • Glossary–3
 - introduction to • 1–2
 - list of • 1–4
- Subset
 - definition of • viii
- SYMBIONT_PROCESS_ID keyword
 - of ANALYZE/AUDIT/SELECT command • 2–3
- SYSPRV privilege • 2–23
- System manager
 - definition of • Glossary–3
 - use of this manual • v
- System messages • A–1
- System Service
 - \$CHANGE_CLASS routine • 3–11
 - \$FORMAT_CLASS routine • 3–9
- System service routines
 - description of • 3–4 to 3–15
 - item lists • 3–4
 - \$PARSE_CLASS routine • 3–7
 - reference section • 3–2
- SYSTEM_LOW • 1–10
- SYSTEM_LOW classification • 1–7

T

Template

- association with printers • 2-24
- showing associations of • 2-33
- using SET TEMPLATE command • 2-5

Template database • 2-23

- creation of • 2-23

Trusted Computing Base (TCB)

- definition of • Glossary-4
-

U

UIC

- in relation to SEVMS • 1-1

UPGRADE privilege

- affect on mandatory access controls • 1-5
- using SET command • 2-6
- with SET AUDIT command • 2-9

User identification code

- see UIC

Using this manual • v

V

VMS

- complementary security techniques of SEVMS • 1-2
- conventions of • viii

VMS documentation

- associated manuals • vi

VMS Security Enhancement Service

- see also VMS SES
- definition of • v, Glossary-4

VMS SES

- description of • v
- see VMS Security Enhancement Service
- see also SES • Glossary-4

VMS SES documentation • v

VMS SES software security consulting package

- components of • v
- definition of • v

VMS SES User's Guide

- description of • v

VOLPRO privilege

- affect on mandatory access controls • 1-5
-

Volume identification • 2-38

W

WIDTH qualifier • 2-24

- of SHOW TEMPLATE command • 2-34

Write access

- definition of • Glossary-4
- implementation of • 1-6

Write-down

- definition of • Glossary-4

WRITE ONLY privilege • 1-5

Write-up

- definition of • Glossary-4
- description of • 1-5

Reader's Comments

Please use this postage-paid form to comment on this manual. If you require a written reply to a software problem and are eligible to receive one under Software Performance Report (SPR) service, submit your comments on an SPR form.

Thank you for your assistance.

I rate this manual's:	Excellent	Good	Fair	Poor
Accuracy (software works as manual says)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Completeness (enough information)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Clarity (easy to understand)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Organization (structure of subject matter)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Figures (useful)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Examples (useful)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Index (ability to find topic)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Page layout (easy to find information)	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

I would like to see more/less _____

What I like best about this manual is _____

What I like least about this manual is _____

I found the following errors in this manual:

Page	Description
_____	_____
_____	_____
_____	_____
_____	_____

Additional comments or suggestions to improve this manual:

I am using Version _____ of the software this manual describes.

Name/Title _____ Dept. _____
Company _____ Date _____
Mailing Address _____ Phone _____

FOLD HERE AND TAPE. DO NOT STAPLE.

igital™



No Postage
Necessary
if Mailed in the
United States

BUSINESS REPLY MAIL
FIRST CLASS PERMIT NO. 33 MAYNARD, MA

POSTAGE WILL BE PAID BY ADDRESSEE

Digital Equipment Corporation
Advanced Technology Products & Services
110 Spitbrook Road, ZK03-3/Z34
Nashua, NH 03062

ATTENTION: Release Engineering SEVMS



FOLD HERE AND TAPE. DO NOT STAPLE.