	•							
	•							
	::					2		••••••
	:					:	-	
 ••••	::					3		••••
••••						3		••••
				 		:		••••
						2		
						:		••••
						ž		••••
						ä		••••
						•		 ••••
				 		•		••••
	•							
							•	
							•	
		0000000					•	••••••
	~						•	

IBM System/3 Disk Sort Reference Manual

Disk Sort Program Numbers: 5702-SM1 (Models 8 and 10) 5703-SM1 (Models 4 and 6) 5704-SM1 (Model 15) 5704-SM9 (Model 15) 5705-SM1 (Model 12)

CCP/Disk Sort Program Numbers: 5703-SM2 (Model 4) 5704-SM7 (Model 15) 5799-ATF (Models 8 and 10) 5799-ATG (Model 12) 5799-ATH (Model 15)

## **Program Product**

SC21-7522-8 File No. S3-33

### Ninth Edition (April 1978)

This is a major revision of, and obsoletes, SC21-7522-7 and Technical Newsletters SN21-5405, SN21-5511, and SN21-5495.

Because the changes are extensive, this manual should be reviewed in its entirety.

This edition applies to the following IBM System/3 programs and to all subsequent versions and modifications until otherwise indicated in new editions or technical newsletters.

Model	Program Name	Program Number	Version	Modification
4	CCP/Disk Sort Program	5703-SM2	13	00
8, 10	CCP/Disk Sort Program	5799-ATF	14	00
12	CCP/Disk Sort Program	5799-ATG	3	00
15	CCP/Disk Sort Program	5799-ATH	6	00
15D	CCP/Disk Sort Program	5704-SM7	2	00
6	Disk Sort Program	5703-SM1	14	00
8, 10	Disk Sort Program	5702-SM1	14	00
12	Disk Sort Program	5705-SM1	4	00
15	Disk Sort Program	5704-SM1	6	00
15D	Disk Sort Program	5704-SM9	2	00
	-			

Changes are continually made to the specifications herein; before using this publication in connection with the operation of IBM systems, consult the latest System/3 Bibliography, GC20-8080, for the editions that are current and applicable.

Requests for copies of IBM publications should be made to your IBM representative or to the IBM branch office serving your locality.

Address comments concerning the contents of this publication to IBM Corporation, Publications, Department 245, Rochester, Minnesota 55901. Comments become the property of IBM.

© International Business Machines Corporation 1970, 1971, 1972, 1973, 1975, 1976, 1978

This manual helps the System/3 programmer fill out the sequence specifications needed in order to run:

- The System/3 Disk Sort program on System/3 Models 4, 6, 8, 10, 12, and 15
- The System/3 CCP/Disk Sort program on System/3 Models 4, 8, 10, 12, and 15

Two coding sheets are discussed in this manual:

- Sequence Specifications, GX21-9089
- Translation Table and Alternate Collating Sequence Coding Sheet, GX21-9096

The *How to Use This Manual* section in Chapter 1 explains the organization of this book.

For ease of illustration, many of the examples in this book use card-like figures to represent records. This does not imply that a card device must be used for input or output in these situations. Any of several input/output devices might be used, depending on which System/3 model and configuration you are using.

#### IBM System/3 5448 Disk Storage Drive

The IBM System/3 5448 Disk Storage Drive on System/3 Models 8 and 10 uses the same program product support as the IBM 5445 Disk Storage. However, a separate system control program feature is required for the 5448. In general, references to 5445 in this manual also apply to 5448. For specific information about 5448 operating characteristics and programming support, see *IBM System/3 5448 Disk Storage Drive Program Reference Manual*, GC21-5168. System/3 Model 4 users should note that:

- System/3 Model 4 is supported by System/3 Model 6 System Control Programming and Program Products. The facilities described in this publication for the Model 6 are also applicable to the Model 4, although the Model 4 is not referenced.
- Not all devices and features available on the Model 6 are available on the Model 4. Therefore, Model 4 users should be familiar with the contents of the *IBM System/3 Model 4 Introduction*, GC21-5146.
- All references to the 5444 disks on systems without 3340 Direct Access Storage Facility also apply to the 5447 disks unless otherwise noted.

System/3 Model 8 users should note that:

- The System/3 Model 8 is supported by System/3 Model 10 Disk System System Control Programming and Program Products. The facilities described in this publication for the Model 10 are also applicable to the Model 8, although the Model 8 is not referenced.
- Not all devices and features available on the Model 10 are available on the Model 8. Therefore, Model 8 users should be familiar with the contents of the *IBM* System/3 Model 8 Introduction, GC21-5114.

System/3 Model 10 Disk System users should note that:

 In this publication the System/3 Model 10 Disk System is termed the Model 10. Without exception, all references to Model 10 apply to the Model 10 Disk System.

System/3 CCP/Disk Sort Program for Models 8, 10, 12, and 15

Appendix I points out the differences between the CCP/ Disk Sort Programs for Models 8, 10, 12, and 15 and the corresponding Disk Sort Program for these systems.

### System/3 Models 12 and 15 users should note that:

- The IBM 3340 Direct Access Storage Facility attaches to the System/3 Model 12 and to the System/3 Models 15B, 15C, and 15D.
- The IBM 3344 Direct Access Storage attaches to the System/3 Model 15D.
- Certain areas on the 3340 and 3344 disks are treated as 5444 disks. These areas are known as 5444 simulation areas and are used for the program libraries and can be used for data files. The remainder of the disk space is known as the main data area and can only be used for data files.
- References in this manual to the 5444, 5445, and 3340 are to be interpreted according to which disk storage device(s) is(are) attached to your system. The following table is used to determine the meaning of the reference:

	· · · · · · · · · · · · · · · · · · ·	****		
	Models 8 and 10	Model 15A	Models 12, 15B, 15C	Model 15D
Reference	Meaning	Meaning	Meaning	Meaning
5444	5444 Disk Storage Drive	5444 Disk Storage Drive	5444 simulation area on 3340	5444 simulation area on 3340 or 3344
5445	5448 Disk Storage Drive or (Model 10) 5445 Disk Storage	5445 Disk Storage	Main data area on 3340	Main data area on 3340 or 3344
3340	Not applicable	Not applicable	Main data area on 3340	Main data area on 3340 or 3344

- All references to the System/3 Model 15 in this manual apply to all models of Model 15 as specified below unless otherwise indicated:
  - For Disk Sort, program number 5704-SM1 for Models 15A, 15B, and 15C; and program number 5704-SM9 for Model 15D.
  - For CCP/Disk Sort, program number 5704-SM7 for Model 15D.

For further information, see the appropriate publication listed under *Related Publications;* for more information about the manuals or the coding sheets, contact your nearest IBM branch office.

### **RELATED PUBLICATIONS**

T (1011.0. (			Order N	umber		
Type of IBM System/3 Publication	Model 4	Model 6	Model 8	Model 10	Model 12	Model 15
Introduction	GC21-5146	GA21-9122	GC21-5114	GC21-7510	GC21-5116	GC21-5094
System Control Program Reference			GC21	-7512	GC21-5130	GC21-5077 (5704-SC1) GC21-5162 (5704-SC2)
OCL and Disk Utilities	GC21	-7516				
Components Reference	GA34	I-0001	GA21-92		1-9236	
Disk Concepts and Planning Guide			GC21-	7571		
Operator's Guide	GC21-5149	GC21-7501	GC21-	7508	GC21-5144	GC21-5075
Messages/Halt Guide GC21-7541		-7541	GC21-	7540	GC21-5145	GC21-5076
Communications Control Program Terminal Operator's Guide	GC21-7580			GC21	1-7580	
CCP Programmer's Reference Manual	GC21-5150			GC21	1-7579	
Program Logic Manuals:				<u> </u>		
Disk Sort and CCP/Disk Sort PLM			LY21-0	0517		
System Control Program PLM	SY21-0502				SY21-0046	SY21-0033
Scheduler PLM						SY21-0035
Data Management PLM		SY21	-0512			SY21-0034

v

## Contents

CHAPTER 1. INTRODUCTION	.1
How to Use This Manual	.1
Important Information for Users of System/3	
CCP/Disk Sort	
System Configuration	. 2
CHAPTER 2. OVERVIEW OF DISK SORT	.3
The Three Types of Sort: Addrout, Tag Along, and	
Summary Tag Along	. 5
Running the Disk Sort or CCP/Disk Sort Program	. 6
Sequence Specifications Sheet	.7
Order of Sequence Specifications	. 8
How to Supply Sequence Specifications	.8
OCL Statements	, 9
File Considerations	10
7-Track Tape Considerations	15
9-Track Tape Considerations	16
Restrictions on the Use of Multifile Tapes (Model 15)	16
How to Supply OCL Statements for the Model 6	16
How to Supply OCL Statements for the Model 10	16
How to Supply OCL Statements for the Model 12	17
How to Supply OCL Statements for the Model 15	17
Timing Considerations	
Programming Considerations	18
Specifications for Tag Along Sort (SORTR)	19
Specifications for Addrout Sort (SORTA)	20
Specifications for Summary Sort (SORTRS)	21
CHAPTER 3. HEADER SPECIFICATIONS	22
Column Summary.	22
Column Descriptions	
Columns 1-2 (page Number) and 3-5 (Line Number)	
Column 6 (Line Type)	
Columns 7-12 (Job)	
Columns 13-17 [Largest Sum (in Bytes) of Control Field	
Lengths for Any Record Type]	23
Column 18 (Ascending or Descending Sequence)	23
Column 26 (Collating Sequence)	
Column 27 (Print Option)	
Column 28 (Output Option for Tag Along Sorts)	24
Columns 29-32 (Output Record Length for Tag Along Sorts).	24
Column 34 (Nonverify Option)	24
Columns 37-38 (Storage Size) - CCP/Disk Sort Model 15	
5704-SM7 and 5799-ATH	
-	
Columns 40-43 (Record Length) — CCP/Disk Sort Only Columns 40-72 (Job Description) or Columns 44-72 (Job	20
Description – CCP/Disk Sort Only)	25
Columns 75-80 (Program Identification/Program Name)	20

CHAPTER 4. RECORD TYPE SPECIFICATIONS		
Column Summary		
Column Descriptions		
Columns 1-2 (Page Number) and 3-5 (Line Number)		
Column 6 (Line Type)	•••	27
Include Sets		
Omit Sets		29
Column 7 (Continuation or Comments)	• •	30
Column 8 (C/Z/D/P/U)		30
Columns 9-16 (Factor 1 Location)		34
Columns 17-18 (Relation)		34
Column 19 (Field or Constant)		
Columns 20-27 (Factor 2 Field).		
Columns 20-39 (Factor 2 Constant)		25
Columns 40-72 (Comments)		
	•••	30
CHAPTER 5. FIELD DESCRIPTION SPECIFICATIONS		27
Column Summary.		
Column Description		
Columns 1-2 (Page Number) and 3-5 (Line Number)		
Column 6 (Line Type)		
Column 7 (Field Type or Comments)		
Column 8 (C/Z/D/P/U/V)		
Columns 7-8		43
Columns 9-16 (Field Location)		44
Column 17 (Conditionally Forced Character)		45
Column 18 (Forced Character)		45
Column 19 (Specifying Replacements for More Than One		
Character)		46
Examples of Using Forced Control Fields		
Columns 20-22 (Overflow Field Length Entry)		
Columns 23-39		
Columns 40-72 (Comments)		
	•••	52
CHAPTER 6. SAMPLE DISK SORT JOBS		52
Record Formats for the Inventory File.		
Record Formats for the Transaction File		
Sample Job 1: Include on Field Relationship		
Header Specifications.		
Record Type Specifications		
Field Specifications		
Sample Job 2: Addrout Sort		
Header Specifications		58
Record Type Specifications		59
Field Specifications		59
Sample Job 3: And Logic-Opposite Control Fields		
Header Specifications.		61
Record Type Specifications		
Field Specifications.		
Sample Job 4: Multiple Include Sets with Force		
Header Specifications.		
Record Type Specifications		
Field Specifications.		
Sample Job 5: Summary Sort-Eliminating Duplicates		
Header Specifications.		
Record Type Specifications		
Field Specifications		68

Sample Job 6: Summary Sort—Insertion of Character	
Data–FDV	. 69
Header Specifications	. 70
Record Type Specifications	. 70
Field Specifications	. 70
Sample Job 7: Negative Values Possible	. 72
Header Specifications	. 72
Record Type Specifications	. 72
Field Specifications	. 73
Sample Job 8: Multiple Input Files	. 74
Header Specifications	. 76
Record Type Specifications	. 76
Field Specifications	. 77
Sample Job 9: Record Selection on Binary Values	. 78
Type 1 Include Sequence	. 78
Type 2 Include Sequence	. 78
Sample Sort Job 9 Description	. 79
Header Specifications	
Record Type Specifications	. 82
Field Specifications	. 82
CHAPTER 7. INTEGER (BINARY) AND REAL NUMBER	
SORTING	. 83
Sample Job 1: Sorting on a Control Field that Contains Either	~~
a Positive Integer or a Positive Real Number	
Header Specification	
Record Type Specifications	
Field Specifications.	. 84
Sample Job 2: Sorting on a Control Field that Contains Only	05
a Positive or Negative Integer	
Header Specification	
Record Type Specifications	
Field Specifications.	.8/
Sample Job 3: Sorting on a Control Field that Contains Only a Positive or Negative Beal Number	88

a Positive or Negative Real Number
Header Specification
Record Type Specifications
Field Specifications
APPENDIX A. CONVERSATIONAL OCL FOR MODEL 6 91
Coding OCL Cycles
The Modify Statement
The Load Cycle
The Build Cycle
The Call Cycle
APPENDIX B. SUPPLYING SEQUENCE SPECIFICATIONS . 100
Interrelationship of Conversational OCL and Sequence
Specifications (Model 6)
Supplying OCL Statements and Sequence Specifications for the
Model 10, the Model 12, and the Model 15

would for, the would fiz, and the wit		
Which OCL and Sequence Specification	on Method to Use for the	
Model 10, the Model 12, and the Mo	del 15 105	

APPENDIX C. COLLATING SEQUENCE
Standard Collating Sequence
Alternate Collating Sequence
Coding Rules
Input Order when ALTSEQ Statements are Used 108
Programming Considerations
Effect of ALTSEQ Statements on Other Coding 108
Sample ALTSEQ Statements
Programming Aids

•••••••••••••••••••••••••••••••••••••••	110
Main Storage Size	
	110
	110
	111
	111 111
	••••
	113
	113
	113 113
Model 6 and Model 10 Timings Only	113
	113
•	115
	115
APPENDIX E. CALCULATING SIZE OF FILES	116
	116
	116
	116
Work File Size Factor	118
	119
	119
5445 Disk Files	120
3340 Disk Files (Model 12 and Model 15)	120
APPENDIX F. MESSAGES	121
APPENDIX G. INSTRUCTIONS FOR EXECUTING THE DISK	
SORT SAMPLE PROGRAM	
Sample Program for Model 6	146
Sample Program for Model 8, Model 10, Model 12, and	
Model 15	147
APPENDIX H. CCP/DISK SORT SPECIFICATIONS	
DIFFERENCES	. 148
CCP/Disk Sort Overview	
File Statement Considerations.	
Multiple Input Files (Model 15 only)	
Output File Over Input File Considerations for Model 4	. 149
Work Record Length	
CCP/Disk Sort Object Program Generation Job Stream	
Example	. 150
CCP Assignment Set Statements Example	. 152
CCP/Disk Sort Execution (Batch Mode) Job Stream	
Example	. 153
APPENDIX I. CCP/DISK SORT PROGRAM FOR SYSTEM/3	
MODELS 8, 10, 12, 15A, 15B, AND 15C	
CCP/Disk Sort Program (Program Number 5799-ATF)	
CCP/Disk Sort Program (Program Number 5799-ATG) CCP/Disk Sort Program (Program Number 5799-ATH)	
CORTONNA SOLL FLOGRAM (FLOGRAM NUMBER STASSAID)	. 104
APPENDIX J. GLOSSARY	. 155
INDEX	157

viii

This publication is designed to help you, the programmer, use System/3 Disk Sort and System/3 CCP/Disk Sort. The CCP/Disk Sort Program is used with the Communications Control Program on the System/3 Model 4 with Program Number 5703-SM2 and Model 15 with Program Number 5704-SM7.

### HOW TO USE THIS MANUAL

Your need for reference material varies with programming experience and familiarity with a particular system. This manual contains four different levels of information:

- 1. Overview of Sequence Specifications shows which columns on the sequence specifications sheet you must consider when you want to sort a disk or tape file.
- 2. Column Summaries list the possible entries for each column on the sequence specification sheet.
- 3. *Column Descriptions* explain the possible entries for each column in greater detail.
- 4. Sample Jobs show how to fill out the sequence specification sheets for typical jobs.<sup>1</sup>

Here is how to use each level:

- Use the *Overview* to see which columns on the sequence specifications sheet you must consider when you want to sort a disk or tape file.
- Use the *Column Summaries* for a quick recall of the possible entries for each column on the sequence specifications sheet.
- Use the *Column Descriptions* when you need a detailed explanation of the entries for a particular column.
- Use the Sample Jobs to review coding techniques for actual jobs.<sup>1</sup>

<sup>1</sup>See Appendix H for CCP/Disk Sort differences.

A column summary and column descriptions are provided for each type of specification:

- Header
- Record type
- Field description

Important Information for Users of System/3 CCP/Disk Sort

System/3 CCP/Disk Sort users should review Appendix H prior to coding your program for the following reasons:

- If you are knowledgeable with System/3 Disk Sort programming and System/3 CCP, Appendix H illustrates the CCP/Disk Sort differences your coding must reflect.
- Appendix H provides a CCP/Disk Sort overview. For more details, refer to the chapter discussions.
- If you are a first time user of System/3, System/3 Disk Sort, or System/3 CCP/Disk Sort, Appendix H provides an orientation to System/3 CCP/Disk Sort for your System/3 Model 4 (5703-SM2) or Model 15 with Program Number 5704-SM7.

Additional information on System/3 CCP/Disk Sort Programs for System/3 Models 8 and 10 (5799-ATF), System/3 Model 12 (5799-ATG), and System/3 Models 15A, 15B, and 15C (5799-ATH) is provided in Appendix I.


### SYSTEM CONFIGURATION

For information concerning the minimum system configuration for disk sort and additional devices supported, see one of the following publications, as appropriate for your System/3 model:


- *IBM System/3 Models 4, 6, 8, 10, and 12 System Generation Reference Manual,* GC21-5126
- IBM System/3 Model 15 System Generation Reference Manual, GC21-7616
- IBM System/3 Model 6 Introduction, GA21-9122
- IBM System/3 Model 8 Introduction, GC21-5114
- IBM System/3 Model 12 Introduction, GC21-5116
- IBM System/3 Model 15 Introduction, GC21-5094

With the IBM Disk Sort or CCP/Disk Sort (also see Appendix H) Program you can:


• Rearrange the records in a disk or tape file:



• Drop records from a disk or tape file:



• Reformat the records in a disk or tape file:



Here is how the Disk Sort or CCP/Disk Sort Program works with the records in your file:

1. Disk sort reads a record from the input file:

1	5	6	<u> </u>	27 30 ↓
	Control field A	Da	ata	Control field B

*Note:* Control fields are the fields you want disk sort to use to sort the records. See *Column 7* under *Field Description Specifications* for a detailed discussion of control fields.

- 2. Disk sort checks your sequence specifications to see whether the record is one you want to sort (often you may not want to sort all the records in the file).
- 3. If the record *is* one you want to sort, disk sort builds a work record, formatting it according to your sequence specifications (the format of the work record is important because it controls the format of the output record).

Assume that your sequence specifications say:

- a. Put the contents of positions 27-30 in the input record into positions 1-4 of the work record.
- b. Put the contents of positions 1-5 in the input record into positions 5-9 of the work record.
- c. Put the contents of positions 6-26 in the input record into positions 10-30 of the work record.

4

The work record disk sort builds would look like this:

1	4	5	9	10	30
			+	*	······
Control	field B	Control field A			Data

See *Column 7, Field Description Specifications* for a more detailed discussion of the work record.

If you are not dropping control fields, they will always precede data fields in the work and output records (see *Column 28—Header Specifications* for a discussion of dropping control fields).

- 4. Disk sort writes all the records you want to sort into the work file.
- 5. Disk sort checks your sequence specifications to see how you want to arrange the records in the output file (ascending or descending order by control fields).
- 6. Disk sort writes the records in the output file in the order you have specified. The only exception is when you want to drop control fields from the output record.

# THE THREE TYPES OF SORT: ADDROUT, TAG ALONG, AND SUMMARY TAG ALONG


There are three types of sort jobs: addrout (address out), tag along (data fields can *tag along* with control fields in the sorted records), and summary tag along (data is summarized in the sorted records).

The output from an addrout sort job consists of 3-byte binary relative record numbers of the records in the input file.

Sorted records

The output for a tag along sort is a file of sorted records. The sorted records can contain:

- Control fields and data
- Control fields only
- Data only




Tag along sort

The output for a summary tag along sort is a file of sorted records. The sorted records can contain:

- Control fields, data fields, and summary data
- Control fields only
- Data fields and summary data
- Summary data fields only

# RUNNING THE DISK SORT OR CCP/DISK SORT PROGRAM



1

- <sup>1</sup>OCL statements are your instructions to the computer.
- <sup>2</sup> Sequence specifications are your instructions to the disk sort program.
   <sup>3</sup> File to be sorted can be an indexed, sequential, or direct disk
- *File to be sorted* can be an indexed, sequential, or direct disk file, or a sequential tape file (or card or 3741 diskette file for Model 15).
- <sup>4</sup>*Work file* is an area on disk where disk sort writes all the records you want to sort. The program can then work with the records there without disturbing the input file.
- <sup>5</sup>Sorted file can contain:
- a. The relative record numbers of the records in the file
- b. Part or all of the records themselves (forming a sequential file)

### SEQUENCE SPECIFICATIONS SHEET

The sequence specifications sheet contains three different kinds of specifications: header, record type, and field description. The sample specifications sheet below shows the location and purpose of all three.

CC27 Display         CC27 Display <th colspan<="" th=""><th>х. <b>Х</b></th></th>	<th>х. <b>Х</b></th>	х. <b>Х</b>
Here you specify the type of sort job you are going to run.	Header specifications	
<u>а + 5 [5] з в юлираниции шерририририририри 10 [5] 5 </u>	).	
Line         Factor 1         Ref.         Factor 2 (Feld, Constant, or Kervourd)         Comments           Univer         5         5         5         6         5         6         6         6         6         6         6         6         7 <th></th>		
Here you specify which of the file's records you want to sort.	Record type specifications	
0 4 6 7 7 7 7 7 7 7 7 7 7 7 7 7 7 7 7 7 7		
Line         Forced         Comments           Unite         50 Control on the second of the s		
Here you specify how you want the records sorted.	Field description specifications	
1       β       1		

### **Order of Sequence Specifications**

The normal order of sequence specifications is:

- 1. Header line
- 2. Record type lines
- 3. Field description lines

This order can vary, however, depending on how many records you want to sort and the format of those records (format refers to the locations, lengths, and types of fields in a record). If, for example, you want to sort all the records in a file — and they all have the same format — you do not have to fill out record type specifications (this is often referred to as implied include-all).

Number of Records to be Sorted	Format of Records to be Sorted	Order of Sequence Specifications
All the records in the file (implied include-all)	All the same	<ol> <li>Header line</li> <li>Field description lines</li> </ol>
Some of the records in the file	All the same	<ol> <li>Header line</li> <li>Record type lines</li> <li>Field description lines</li> </ol>
All or some of the records in the file	Several different formats	1. Header line       For first type         2. Record type lines       of record         3. Field description lines       For second type         4. Record type lines       For second type         5. Field description lines       of record format         6. Record type lines       One set for each additional         7. Field description lines       type of record format <sup>1</sup>

ications must be grouped (one set of record type and field description lines for each format type). The records themselves can be in any order.

For detailed information on how to include or omit certain records when you are sorting a file, see *Column 6* under *Record Type Specifications.* 

### How to Supply Sequence Specifications

You can supply the sequence specifications from:

- The device you are using to supply the OCL statements
- An OCL procedure containing the LOAD, FILE, and RUN statements for the job (the OCL procedure may or may not contain other jobs)
- A source library module

Appendix B summarizes:

- The advantages and disadvantages of each of these methods
- The interrelationship of the three methods of supplying sequence specifications and three of the OCL cycles (LOAD, BUILD, and CALL)

*Note:* Regardless of the method used to read the sort specification statements, the system input device is dedicated to the partition in which the sort is running until all such statements are read.

8

### **OCL STATEMENTS**

Before your system can run a sort job, it needs certain information about the disk sort program, the sequence specifications for the job, and the files involved in the job (every sort job uses a minimum of three files: an input file, a work file, and an output file). You supply this information in OCL statements. Here is the information you must supply:

### About the Sequence Specifications

- 1. How you are going to enter the sequence specifications (for example, keyboard for the Model 6, MFCU for the Model 10, 1442 or MFCU for the Model 12, or display station or MFCU for Model 15).
- Where you want any computer-to-operator messages printed.

#### About the Program

- 1. Name of the program you want to run (\$DSORT).
- 2. Disk drive location of the disk sort program.

#### About the Input File

- Name of the file you want to sort. The FILE statement name must be INPUT (or INPUT1,..., IN-PUT8 for Model 12 or Model 15). However, if the file name is not INPUT (or INPUT1,..., INPUT8 for Model 12 or Model 15), use the LABEL keyword to identify the actual file name.
- 2. Unit assignment of the file you want to sort:
  - a. All Models Except Model 4: Removable disk 1 or 2 (R1 or R2) or fixed disk 1 or 2 (F1 or F2) for the 5444

*Model 4:* Removable disk R1 or fixed disk R2, F1, or F2 for the 5447

- b. *Model 10:* Drive 1 or 2 (D1 or D2) for the 5445 or fixed disk 1 or 2 (F1 or F2) for the 5448.
- c. *Model 12:* Drive 1 or 2 (D1 or D2) for the 3340 main data area
- d. *Model 15:* Drive 1, 2, 3, or 4 (D1, D2, D3, or D4) for the 5445 or 3340
- e. *Model 15D:* Drive 3 [D31 (D3), D32, D33, and D34] or Drive 4 [D41 (D4), D42, D43, and D44] for the 3344.
- f. Drive 1, 2, 3, or 4 (T1, T2, T3, or T4) for tape
- g. Also supported on the Model 15 are MFCU, MFCM, 1442, 2501, and 3741
- h. If the file is spooled to disk, sort uses the file as if it were coming from the device of original entry.

- 3. Name of the disk pack or tape that contains the file.
- 4. If you use tape, specify UNIT, BLKL, and RECL.
- 5. If you use the 3741, specify RECL (Model 15 only).

### About the Work File<sup>1</sup>

- 1. Name of the file you are going to use as a work area. The FILE statement name must be WORK, however, if the name of your file is not WORK, use the LABEL keyword to indicate the actual name of the file.
- 2. Disk drive location (unit) of the work file:
  - a. All Models Except Model 4: Removable disk 1 or 2 (R1 or R2) or fixed disk 1 or 2 (F1 or F2) for the 5444 Model 4: Removable disk R1 or fixed disk R2,

F1, or F2 for the 5447

- b. *Model 10:* Drive 1 or 2 (D1 or D2) for the 5445 or fixed disk 1 or 2 (F1 or F2) for the 5448.
- c. *Model 12:* Drive 1 or 2 (D1 or D2) for the 3340 main data area
- d. *Model 15:* Drive 1, 2, 3, or 4 (D1, D2, D3, or D4) for the 5445 and 3340
- e. *Model 15D:* Drive 3 [D31 (D3), D32, D33, and D34] or Drive 4 [D41 (D4), D42, D43, and D44] for the 3344.
- 3. Name of the disk pack that contains the file.
- Number of tracks in the file. (Do not specify number of records.)
- 5. Status of the file. The work file should be a scratch file since you won't need its information after a sort job.

*Note:* The work file must be online at all times during the sort run.

<sup>&</sup>lt;sup>1</sup> If the file you want to use is an old (temporary) file, you must also supply the location at which the file begins.

### About the Output File<sup>1</sup>

- Name you are going to call the sorted file. The FILE statement name must be OUTPUT; however, if the name of your file is not OUTPUT, use the LABEL keyword to indicate the actual name of the file.
- 2. Unit assignment of the sorted file:
  - a. All Models Except Model 4: Removable disk 1 or 2 (R1 or R2) or fixed disk 1 or 2 (F1 or F2) for the 5444

*Model 4:* Removable disk R1 or fixed disk R2, F1, or F2 for the 5447

- b. *Model 10:* Drive 1 or 2 (D1 or D2) for the 5445
- c. *Model 12:* Drive 1 or 2 (D1 or D2) for the 3340 main data area
- d. *Model 15:* Drive 1, 2, 3, or 4 (D1, D2, D3, or D4) for the 5445 or 3340
- e. Drive 1, 2, 3, or 4 (T1, T2, T3, or T4) for tape
- f. Model 15D: Drive 3 [D31 (D3), D32, D33, and D34] or Drive 4 [D41 (D4), D42, D43, and D44] for the 3344.
- 3. Name of the disk pack or tape on which you are going to put the sorted file.
- 4. Number of records or tracks in the file.
- 5. Status of the file. If the file exists before this sort, it cannot have permanent status. If the file is built during the sort, it can have temporary or permanent status.
- 6. If tape is used, UNIT, BLKL, and RECL must be specified.

### Notes:

- 1. You may not have your output file deferred if it is a split cylinder file.
- 2. If the END parameter is not used, disk sort defaults to rewinding and unloading tape files.

#### **File Considerations**

#### Input: General

The input file contains records to be sorted. Any file created by System/3 data management can be used as input to disk sort; for example, an RPG II file or a file from a previous disk sort run. The disk file may have been created by any processing method – sequential, indexed, or direct. A tape file must have been created sequentially. Since direct file areas are set to blanks before the file is created, you should test for and omit blank records. You can do this by testing a position that is known never to contain blanks.

### Input: Model 6 and Model 10

The FILE statement name must be INPUT. However, the actual file need not be called INPUT because the LABEL keyword allows you to identify the file you will be sorting. The input file may be multivolume (online or offline). However, for SORTA jobs, when the input file is processed by an RPG II program with your sorted addrout file, the input file must be online.

The volumes containing the INPUT file must be mounted online *prior* to running disk sort. However, if the input file is offline multivolume, (more than one volume assigned to a removable unit), only the first volume assigned to each unit is required to be mounted. If the input file is not online prior to running, the job will end with message SD 105 (INPUT FILE NOT ONLINE) followed by a CD45 halt (Model 6) or a 25 halt (Model 10).

If your input file is ASCII and ASCII-YES is not specified on the input file card, all data is treated as if it is EBCDIC. EBCDIC and ASCII data cannot be mixed in a sort run. An ASCII input file requires an ASCII output file and an EBCDIC input file requires an EBCDIC output file.

When ASCII is specified for input and output, packed data should not be specified in the sort specifications since ASCII does not support packed data.

Variable-length blocks are not allowed by disk sort tape I/O; the job will end if they are encountered.

#### Multiple Input: Model 6 and Model 10

Disk sort supports multiple file input to the same extent that System/3 data management supports multiple file input. For more information on this subject, see the multivolume file discussion in the *IBM System/3 Model 10 Disk System Control Programming Reference Manual*, GC21-7512 or the *IBM System/3 Model 6 Operation Control Language and Disk Utility Programs Reference Manual*, GC21-7516.

Restrictions for multiple file input to disk and tape files are:

*Disk Multiple File Input:* Multiple files can be used as input if they are made to appear as multivolume files with the following restrictions:

- 1. Labels must all be the same.
- 2. Record lengths must all be the same.
- 3. Files reside on different packs.

<sup>&</sup>lt;sup>1</sup> If the file you want to use is an old (temporary) file, you must also supply the location at which the file begins.

Tape Multiple File Input (Model 10): Multiple files can be used as input if they are specified as multivolume files with the following restrictions:

- 1. RECL and BLKL must be the same.
- 2. Record format must be the same.
- 3. Unlabeled or nonstandard tape files.
- Files must have the same attributes (such as, use of a 9-track, 7-track, ASCII, EBCDIC, parity, density, CONVERT, or TRANSLATE).

*Note:* Standard labeled tape files cannot be used for multiple file input.

Input: Model 12

Input can be from either of the following devices:

- 3340 Direct Access Storage Facility
- 3410/3411 Magnetic Tape Subsystem

Up to eight files can be used as input using any combination of the preceding devices. The file names must be: INPUT or INPUT1 (but not both), INPUT2, INPUT3, INPUT4, INPUT5, INPUT6, INPUT7, and/or INPUT8.

The files will be processed INPUT (or INPUT1) serially to INPUT8 regardless of the order of the OCL FILE statements. The lowest numbered input file will be processed fully first, then the next numbered input file will be processed in its entirety, then the next until all the files have been individually processed in sequence. For a particular disk sort run, the input files do not have to be numbered serially; that is, the file names may be INPUT3, INPUT5, and INPUT8, or a particular run could have just INPUT8 as the input file.

All single-volume disk files must be online prior to running disk sort. However, when using multivolume offline disk files, only the first volume assigned to each unit must be mounted prior to running disk sort. When using 3340 multivolume offline disk files, D1 cannot be used.

Input record length is defined as the record length used for the disk and/or tape files.

Special Considerations: When more than one input file is used, the following must be considered:

- Addrout sort is not allowed.
- Auto allocation of the work file should be used with caution. For best performance, use a work file statement.
- The record lengths of all disk or tape files must agree. This is not true for block lengths. Tape files may have different block lengths.

Data Considerations: When running in a multiple device mode, the data restrictions for any one input device apply to all input devices. For example, if disk input is combined with a 7-track translate input file, packed fields should not be used in the disk sort specifications since a 7-track translate record can contain only the System/3 64-character set.

Input can be mixed EBCDIC and ASCII with either EBCDIC or ASCII output. However, when ASCII is specified, packed data should not be specified in the disk sort specifications since ASCII does not support packed data.

### Input: Model 15

Input can be from any of the following devices:

- 5444 Disk Storage Drive
- 5445 Disk Storage
- 3340 Direct Access Storage Facility
- 3344 Direct Access Storage (Model 15D only)
- 3410/3411 Magnetic Tape Subsystem

*Note:* For the following devices, use a device independent FILE statement.

- 1442 Card Read Punch
- 2501 Card Reader
- 3741 Data Station or 3741 Programmable Work Station directly attached
- 2560 Multi-Function Card Machine (MFCM) or
   5424 Multi-Function Card Unit (MFCU)

Up to eight files can be used as input using any combination of the preceding devices. The file names must be: INPUT or INPUT1 (but not both), INPUT2, INPUT3, INPUT4, INPUT5, INPUT6, INPUT7, and/or INPUT8.

The files will be processed INPUT (or INPUT1) serially to INPUT8 regardless of the order of the OCL FILE statements. The lowest numbered input file will be processed fully first, then the next numbered input file will be processed in its entirety, then the next until all the files have been individually processed in sequence. For a particular disk sort run, the input files do not have to be numbered serially; that is, the file names may be INPUT3, INPUT5, and IN-PUT8, or a particular run could have just INPUT8 as the input file.

Card input files will have a record-length characteristic of the device. If card input files are used with disk or tape files, the card input is truncated or padded on the right with blanks to the record length specified for the disk or tape files.

Single-volume disk files need not be online prior to running disk sort. However, when using multivolume offline disk files, the first volume assigned to each unit must be mounted prior to running disk sort. When using 3340 multivolume offline disk files, D1 cannot be used. Input record length is defined as the record length used for the disk and/or tape files. If the 3741 and/or cards are the only input, the input record length is the largest specified for the 3741 or 80 or 96 for card input — whichever is largest.

Special Considerations: When more than one input file is used, the following must be considered:

- Addrout is not allowed.
- Auto allocation of the work file should be used with caution. For best performance, use a work file statement.
- The record lengths of all disk (5444, 5445, or 3340) or tape files must agree. This is not true for block lengths. Tape file may have different block lengths.

Data Considerations: When running in a multiple device mode, the data restrictions for any one input device apply to all input devices. For example, if disk input is combined with 5424 MFCU input, packed fields should not be used in the disk sort specifications since 96-column cards can contain only the System/3 64-character set.

Input can be mixed EBCDIC and ASCII with either EBCDIC or ASCII output. However, when ASCII is specified, packed data should not be specified in the disk sort specifications since ASCII does not support packed data.

Considerations for Writing the Output File Over the Input File: If the output file is to be written over the input file (load to old), the output file will be scratched at the end of job under the following conditions, as though RETAIN-S had been specified for the output FILE statement:

- 1. A pack containing an input file is not online at the start of the job (deferred mount)
- 2. RETAIN-S is used on the FILE statement for the *input* file

To avoid this problem, use RETAIN-T for the input FILE statement.

### CAUTION

When running disk sort program (5704-SM9) using output over input, take care to ensure that another partition does not share the file to be overlaid during sort execution. If this condition occurs, sort may not be able to reopen the file as an output file at output time. This may result in an unrecoverable halt.

### Work File

The work file is generally an area on disk which you have set aside as a work area. The disk sort program uses this area as working storage during the sorting process.

The FILE statement name must be WORK. If the name of the work area is not WORK, use the LABEL keyword to indicate the file you will be using.

A work file should be given scratch status (RETAIN-S), because it is normally created during the sort and has no function afterwards. It is always allocated with a multivolume attribute, even though its FILE statement may indicate single volume.

The work file may be multivolume, but all of the volumes must be online. If either the input or output files are multivolume offline, the removable units containing these multivolume offline files may not be used for the work file.

The work file may be specified on the 5444 or 5445 drives but not on both. An error occurs if work files are allocated on both 5444 and 5445 drives.

When specifying the work file on the 3340 (Model 12 and Model 15), be certain to specify only the 3340 main data area or the simulation area, but not both.

When a new output file is specified and a work FILE statement is given with the same unit as the output file, a halt can occur. The halt is issued when the space allocated for the work file overlaps the area where the new output file is to be located. To avoid the halt, either omit the work FILE statement and let automatic allocate handle the work file or specify locations for both the work file and new output file.

Disk sort work files are opened with multivolume file attributes. If RETAIN-S is used for sort with Model 15 data packs, no problems are encountered. However, if a System/3 Model 6 or Model 10 data pack is used on Model 15 and a nonmultivolume file is attempting to overlay an old System/3 work file and you are using all the original work FILE parameters (LABEL, TRACKS, LOCATION, etc), a terminal error will occur.

When a work file statement is specified on Model 15 systems for 3340s (D1, D2, D3, D4), the verify option is taken from the file statement. Column 34 of the sort header statement is ignored.

### Automatic Work File Allocation

If the FILE statement is omitted from the disk sort OCL, disk sort uses the automatic allocation function to allocate from one to a maximum of four scratch areas, each on a different drive. If four scratch areas are not available, disk sort attempts to allocate three, and so on. The scratch areas are allocated from:

1. Available 5445 packs or 3340 areas

2. Available 5444 fixed and removable packs

*Note:* See chart in the preface of this manual for the disk storage drives applicable to a particular system.

The first choice of the automatic allocation function is the 5445 Disk Storage or the 3340 Direct Access Storage Facility. If a 5445 or 3340 cannot be used, automatic allocation tries to find space on the 5444 disks.

Automatic work file allocation uses scratch areas from the available disk packs. A disk pack is considered available if the pack does not need to be removed while disk sort is executing.

On any given drive, the automatic allocation selects the largest contiguous disk area available. Therefore, a job being executed in another program level or partition may not find enough disk space available. This condition can be minimized to some extent if the disk packs have been fragmented; that is, if a file is intentionally located in the middle of a pack, there will be two contiguous areas instead of one. The degree of pack fragmentation and the location of the fragmented files must be evaluated by each user.

All automatically allocated scratch areas (work file areas) are returned to system use after the disk sort run is completed.

#### Notes:

- Disk sort may exhaust the work areas selected by automatic work file allocation. When this occurs, sort issues the message WORK FILE TOO SMALL. To bypass this condition, increase the size of the free areas or specify the work area with a FILE statement.
- 2. When running a disk sort job using automatic work file allocation, never change packs unless requested to do so by a message.
- 3. The verify option in column 34 of the header statement applies to any automatically allocated work file.

### Automatic Work File Allocation with Multiple File Input (Model 12 and Model 15)

If more than one input file is assigned to a specific device type (5445 or 3340 or the 5444), then any unit of that type that contains an input file will not be used for automatic work file allocation.

For example, if filename INPUT is assigned to unit D1, INPUT3 to unit R2, and INPUT7 to unit D2, units D1 and D2 are not available for automatic allocation since more than one file is assigned to the 5445.

Note: Unit R2 is available since only one input file was assigned to that device type.

### Directed Automatic Work File Allocation (Model 12 and Model 15)

In order to limit or select the 5444, 5445, or 3340 drives that are available to disk sort for automatic work file allocation, you can use a SWITCH OCL statement. The SWITCH statement consists of eight characters; one for each of the eight external indicators (U1-U8). The first or leftmost character gives the setting of indicator U1; the second gives the setting of U2; and so on.

File Allocation			Indi	cator			
	U1&U2	U3	U4	U5	U6	U7	U8
5444 directed	01	x	x	X	R1	R2	F2
5445/3340 directed	11	×	X	D1	D2	D3	D4
X = Not used				<u></u>	• · · ·		•

U1 and U2 = 00No request 01 5444 directed auto allocate is requested 10 No request 11 5445/3340 directed auto allocate is requested Not used

> When set to a 1, the unit requested is considered available for auto allocation of the work file

When requesting a 5444 directed auto allocation, U1 must be 0; U2 must be 1; and U6, U7, and/or U8 can be set to 1.

Note: For a 5444 directed auto allocate, F1 is always considered available for auto allocation of the work file. If U6, U7, and U8 are all set to 0, then only F1 is considered for auto allocation of the work file.

When requesting a 5445/3340 directed automatic allocation, U1 and U2 must be set at 1 and at least one of U5, U6, U7, and U8 must be set to 1.

For example, if you want to direct automatic allocation of the work file to D1 and D2, the SWITCH statement would be:

### // SWITCH 11001100

To direct automatic allocation to R1 and F1, the SWITCH statement would be:

### // SWITCH 01000100

The SWITCH statement must be included after the LOAD or CALL statement and before the RUN statement.

Directed auto allocate does not ensure that space is available on the desired drives; it only directs disk sort requests for work space to these drives.

If the units indicated on the SWITCH statement for a 5445/3340 directed auto allocate are not available, automatic allocation takes place on all available 5444 packs.

If the SWITCH statement is in DSORT OCL, it is not left over from a previous job. It only appears and executes, for a job, when you request it. It will not repeat itself in subsequent job OCL.

Note: For 5444 directed auto allocate, allocation takes place on F1 since F1 is always considered.

### **Output File**

The output file contains the sorted file. The disk file can have sequential organization only. Output of the program is in one of three formats:

- Tags or addrout
- Tag along
- Summary tag along

U3 and U4

and U8

U5, U6, U7,

The file statement name must be OUTPUT. The LABEL keyword can be used to identify the actual file being used.

If the output file exists before the sort (it is old), it cannot have permanent status since you cannot write into a permanent file. However, if the output file is built during the sort, it can have permanent or temporary status.

The output file may be multivolume (online or offline). However, for SORTA jobs, when the input file is processed, the sorted addrout file must be online.

Deferred mounting of the output file is allowed (notice that this does not refer to the system OCL DEFER parameter). This means that the output file does not have to be online prior to running disk sort. The output file specified in the FILE statement may be old or new.

One use of deferred output mounting is to use the same removable unit(s) for both the input and output files, but with the input and output files on different packs. In this case, the shared removable units may not be used for the work file. For example:

1		4					в				1	2				1	6				2	0				24	4				2	В				32	2			3	36				2	40	)			2	44				4	8				53	2				56	3			f	60	)	
7	É	Т	Τ	Γ		Τ	T			Γ	T	Τ			Γ	Τ	Τ		Γ	Γ	Τ	Τ				Γ	T	Τ	٦		Γ	Τ	Ι				Γ	T		Ι			Т	Τ	٦		Γ	Τ	Τ	Τ					T	T	Τ			Ι	I	T			Γ	Γ	Τ	Т	Τ	٦		
17	1	ι	0	A		5		\$	D	5	Ī	5	R	1	١.	ł	-	1		Γ	T	T	T				T	1			Г	t	1				T	T					T	T			Γ	T	T					T	T	T				Γ	T	Ť				Γ	T	Ť	1		Ē	
1	1	F	I	L			T	N	A	N	l	Ξ	-	I	1	1	p	υ	T	Ī,	F	>	A	c	K	-	·	٩	A	A	A	1	A	A	,	U	k	d I	ſ	T	-	F	Z.	ı	,	R	E	1	rl	A	I	N	-	Ī	t	1			Γ	T	T	t				T	T	t	1		ſ	
Ζ	/	F	I	1	E			N	A	N	1	Ε	-	Y	1	1	R	K	,	P	1		2	K	-	F	Ī		X	E	I	)		,	υ	N	h	ŀ	T.	-	F	1	Ι,	ŀ	T	R	A			2	S	-	1	Q	۶,	1	R	E	7	A	1	đ	N	_	S	Ţ	T	T			Ē	
17	1	F	I	1	E			N	A	5	(	E	-	0	U	ī	T	P	V	1	٦,		P	A	c	٢	Į.	-	B	B	E	5	3	в	B	,	k	1	V	L	T	-	F	7	1	,	ī	1	2	A	С	K	S	-	1	1	ø	1	R	E	h	ī/	Ą	Ι	N	F	1	r	T		Ī	
Ν	/	R	U	In	ſ	T	T			ľ	Ī				T	T	1			Γ	T	T				Γ	T				Γ	T	1					T	T				T	T			T	T	ŀ					T	T	T				Γ	T	T			Γ	T	T	T	1		-	
		Т	Т	T	ŀ	T	1			Γ	T			Γ	T	T	1		Г	Г	T	T	1			Γ	T	1			Т	T	1				T	T	1	1			T	T			T	T	T	1			1	Γ	T	T			Γ	T	1	t			Γ	T	T	t	1		Ē	

In this case, pack AAAAAA must be mounted on R1 prior to running disk sort. The mounting of pack BBBBBB on R1 is deferred until later. R1 may not be used for the work file.

Disk sort defaults to rewinding and unloading tape files.

Variable length blocks are not allowed by disk sort tape I/O; the job ends if they are encountered.

*Note:* In the output file, the order of records having duplicate control fields is unpredictable. This does not imply that the output is incorrect, however, since the control fields were in order.

#### 7-Track Tape Considerations

If nonstandard and unlabeled tapes are used, extreme care must be taken when creating a file using converter, translator, and parity parameters. Since no labels are given with block and record sizes on this type of tape, identical FILE statements are necessary each time the 7-track tape is used as input for a job. If an error does occur, disk sort cannot recognize the error. No diagnostic is given.

If standard labeled tapes are used, identical FILE statements are still necessary each time the same 7-track tape is used as input for another job. Since there are labels giving block and record sizes, disk sort can diagnose errors if identical FILE statements are not given.

If 7-track tape is used for either input or output, the converter or translator must be used. Refer to the *IBM* System/3 Models 8, 10, 12, and 15 Components Reference Manual, GA21-9236, for a discussion of the converter and the translator.

The translator cannot be used if output is 7-track tape and packed data or summary data specifications are used.

If input is 7-track tape with the translator on, then include, omit, and field specifications with packed data are not allowed.

If SORTA (addrout) sort is specified, output cannot be 7-track tape.

#### 9-Track Tape Considerations

A terminal error occurs if the tape file is ASCII and ASCII-YES is not specified for both the input file and the output file.

If the output for a SORTA (addrout) sort is to be on tape and ASCII translate has been specified, a terminal error is generated and the sort job ends.

For tape output from an addrout sort, the logical record length (RECL-on file statement) must be 18 positions.

#### **Restrictions on the Use of Multifile Tapes (Model 15)**

You must adhere to the following restrictions when using multifile tape volumes:

- 1. All files in the volume must be labeled in the same manner; that is, all must be standard labeled files or all must be unlabeled files.
- 2. All files in the volume must be recorded in the same density.
- 3. All files in the volume must be recorded in the same mode (translate, convert, or parity).
- 4. If the last file on a multifile reel is continued on a subsequent reel, the two reels constitute an aggregate. The restrictions in 1-3 apply to all volumes of the aggregate. In addition, all volumes of the aggregate must be either 7- or 9-track (7-track and 9-track reels may not be mixed in the same aggregate).
- Standard labeled 7-track tapes, if prepositioned, should be prepositioned to a point just before a HDR1 record. Otherwise, tape data checks or runaway may occur.

Refer to the *IBM System/3 Model 15 System Control Pro*gramming Reference Manual, GC21-5077 and System/3 Control Programming Concepts and Reference Manual, GC21-5162, for discussions of tape multifile volumes. How to Supply OCL Statements for the Model 6

Installations without an Online Data Recorder or a 3741 Data Station: If your installation does not have an online data recorder or a 3741 Data Station, you will use conversational OCL to give the system the information it needs to run the disk sort program.

Appendix A summarizes:

- Which OCL cycle to use (depending on the type of sort you want to do)
- How to respond to the keywords in each cycle

Installations with an Online Data Recorder or 3741 Data Station: If your installation has (1) an online data recorder (IBM 5496 Data Recorder or IBM 129 Data Recorder), (2) a directly attached 3741 Data Station, or (3) a directly attached 3741 Programmable Work Station, you can also supply OCL statements on 96-column punched cards, 80column punched cards, or 96-byte diskette records.

The IBM System/3 Model 6 Operation Control Language and Disk Utility Programs Reference Manual, GC21-7516, explains how to code OCL statements on cards. To supply OCL statements on cards, you must establish the data recorder as the OCL input device. Instructions on how to do this are contained in the IBM System/3 Model 6 Operator's Guide, GC21-7501. To supply OCL statements from a diskette, refer to the IBM System/3 3741 Reference Manual, GC21-5113.

With or without an online data recorder, OCL statements and error messages will be printed out on whatever output device you specify in your LOG statement at IPL. (See the *IBM System/3 Model 6 Operator's Guide*, GC21-7501, for detailed discussion of the IPL procedure.)

### How to Supply OCL Statements for the Model 10

You can supply OCL statements via the device you select as the system reader (the console keyboard, 1442, MFCU1, MFCU2, or 3741). For a discussion of selecting the system reader, see the *IBM System/3 Model 10 Disk System Operator's Guide*, GC21-7508.

To supply OCL statements from the diskette, refer to the *IBM System/3 3741 Reference Manual*, GC21-5113.

### How to Supply OCL Statements for the Model 12

You can supply OCL statements via the device you select as the system reader (the console keyboard, 1442, MFCU1, MFCU2, or 3471). For a discussion of selecting the system reader, see the *IBM System/3 Model 12 Operator's Guide*, GC21-5144.

To supply OCL statements from the diskette, refer to the *IBM System/3 3741 Reference Manual*, GC21-5113.

### How to Supply OCL Statements for the Model 15

You can supply OCL statements via the device you select as the system reader (1442, 2501, MFCU1, MFCU2, console, MFCM1, MFCM2, or 3741). For a discussion of selecting the system reader, see the *IBM System/3 Model 15 Operator's Guide*, GC21-5075.

### TIMING CONSIDERATIONS

The time it takes to sort a file depends on these factors:

- 1. How much main storage you assign for the program's use. The larger the main storage allocation, the less time it takes to run a sort job.
- 2. Number of records you want to sort. The greater the number of records, the longer it takes to sort them.
- 3. Size of the records. The larger the records, the longer it takes to sort them.

- 4. Number of sequence specifications in the sort program. The greater the number of sequence specifications, the longer it takes to run the sort job.
- 5. Whether you are using an alternate collating sequence. An alternate collating sequence can increase the time it takes to run the sort job.
- 6. Where the files are located on the disk. If the disk arm has to make many extra movements, the sort time will increase. This factor is especially significant for jobs with multivolume files.
- 7. Order of the control fields in the input record.
- 8. Whether or not automatic work file allocation is being used.
- 9. Whether you are using the nonverify option. By using this option, data written on the work file will not be verified. The result is a decrease in the time it takes to sort a job.

Each of these factors is discussed in detail in Appendix D.

### **PROGRAMMING CONSIDERATIONS**


	Addrout Sorts (SORTA)	Tag Along Sorts (SORTR, SORTRS)
Core Storage Requirements	Less than tag along sort	More than addrout sort
Work File Size	Need only be big enough to hold control fields and relative record numbers <sup>1</sup>	Must be big enough to hold entire file
Sorted Output	Relative record numbers only	Sorted output records can contain data only, control fields only, or both data and control fields
Input File	Input file should not be overlaid by output file	Input file can be overlaid by output file <sup>2</sup> (the input file can double as the output file)
Job Time	Usually shorter	Usually longer

<sup>1</sup>This lets you sort large files without changing packs.

<sup>2</sup>The space for the output file may be the same as that of the input file. In other words, the output file may overlay the input file. However, good programming practice is to never overlay a file you want to sort, unless you have first made a backup copy of the file. When using the input file as the output file, you must specify the same space (number of records or tracks), location, and label.


### SPECIFICATIONS FOR TAG ALONG SORT (SORTR)

The shaded columns are the ones you must consider for a tag along sort job.




### SPECIFICATIONS FOR ADDROUT SORT (SORTA)

The shaded columns are the ones you must consider for an addrout sort job.



### SPECIFICATIONS FOR SUMMARY SORT (SORTRS)

The shaded columns are the ones you must consider for a summary sort job.



## Chapter 3. Header Specifications

Header specifications tell disk sort:

- What type of sort you want to do (addrout, tag along, or summary tag along)
- How you want to format (arrange) the sorted file

### **COLUMN SUMMARY**

 What, if any, system information you want printed (to aid you in error checking)

Remember, use only one header line for each sort job.

	Columns	Entries	Explanation
	1-2	00-99	Page number
	3-5	000	Header line number
1	6	Н	Header line identification
	7-12	SORTA	Addrout sort job
		SORTR	Tag along sort job
Ł		SORTRS	Summary tag along sort job
	13-17	1-256	Longest control field used in sorting the records
	18	A	Records in sorted file to be in ascending order by control fields
		D	Records in sorted file to be in descending order by control fields
•	19-25	Blank	Not used in disk sort jobs
	26	Blank	Use standard System/3 collating sequence in compare operations
		S	Use an alternate System/3 collating sequence in compare operations ALTSEQ statements will define the collating sequence to be used
	27	0 or blank	Print: Sequence specification lines Diagnostic messages Program-status messages Action messages
		1	Print: Program-status messages Action messages
		2	Print action messages only
		3	Print nothing
	28	Blank	Keep control fields in output records in tag along sort jobs
,		X	Drop control fields from output records in tag along sort jobs
{	29-32	1-4096	Length of output records in tag along sort jobs
	33	Blank	Not used in disk sort jobs
	34	N	Data written on the work file will not be verified
	35-36	Blank	Reserved for system use
	37-38	12-48	Storage size to execute the object module in multiples of 2K (Model 15 CCP/Disk Sort [5704-SM7] only)
	39	Blank	Reserved for system use except CCP/Disk Sort
		С	Indicates task chaining and a record length to follow (Model 15 CCP/Disk Sort [5704-SM7] only)
		R	Indicates a record length to follow (CCP/Disk Sort only)
	40-43	nnn	Input file record length — right justified with or without leading zeros (CCP/Disk Sort only)
	40-72	Any System/3 characters	Comments except CCP/Disk Sort
	44-72	Any System/3 characters	Job description for CCP/Disk Sort
	73-74	Blank	
	75-80	Alphameric characters	CCP/Disk Sort object program name
	The second s		

Columns that must be filled in

Columns that must be filled in for a tag along sort

### **COLUMN DESCRIPTIONS**

#### Columns 1-2 (Page Number) and 3-5 (Line Number)

Page number (columns 1-2) and line number (columns 3-5) form a 5-digit sequence number. As the program reads sequence specifications, it checks the sequence numbers to make sure they are not in descending order. If the numbers are in descending order (for example, if page 02 specifications come before page 01 specifications) and specifications are being printed, the program will print a warning next to the line. After a warning is issued (the letter S) the program continues reading the rest of the specification lines and then halts and waits for further instructions from the operator. The operator can either continue or end the job.

Because page number applies to all lines on a page, columns 1-2 appear only once, in the upper right corner of the page. You number the pages in ascending order.

The line number of the header line is always 000 and is preprinted on the coding sheet.

### Column 6 (Line Type)

Column 6 of the header line contains a preprinted H to identify the line.

### Columns 7-12 (Job)

Columns 7-12 tell the program what type of sort job you want to do. SORTA means addrout sort. SORTR means tag along sort. SORTRS means summary tag along sort.

Columns 13-17 [Largest Sum (in Bytes) of Control Field Lengths for Any Record Type]

To calculate this entry:

- Add together the lengths of the *control* fields (N, O, or F in column 7 of field specifications) for *each* type of input record.
- 2. Place the *largest* of these totals in columns 13-17. (Your entry must not exceed 256.)

For more information, see *Control Fields* under *Column 7*, *Field Description Specifications*.

### Column 18 (Ascending or Descending Sequence)

Control fields control the sequence of records in the sorted output file. Your column 18 entry indicates the sequence in which you want the records sorted:

Col. 18 Entry	Sequence
А	Ascending sequence by control field
D	Descending sequence by control field

#### Column 26 (Collating Sequence)

Column 26 specifies the collating sequence you want disk sort to use in compare operations. (Compare operations determine whether one character is equal to, greater than, or less than another character.)

### Standard Collating Sequence

A blank in column 26 tells the system to use the standard System/3 collating sequence. There are slight variations in the standard collating sequence depending on whether you are using both the zone and digit portions of the characters in your records, the zone portions only, or the digit portions only. Appendix C shows the complete collating sequence for each situation.

#### Alternate Collating Sequence

An S in column 26 tells the program you want to change the standard collating sequence. To do this you must supply ALTSEQ statements immediately following the header specifications (Appendix C tells you how to code ALTSEQ statements).

Do not use a packed or unpacked factor 1 in an include or omit record type specification (P or U in column 8) if you specify an alternate collating sequence.

*Note:* Generally, the only users of alternate collating sequences are European firms that want to insert special alphabetic characters (such as the German ä, ö, and ü and the Spanish ñ) into the standard System/3 collating sequence.

### **Column 27 (Print Option)**

The disk sort program can print:

- Sequence specification lines
- Diagnostic messages, for any errors in sequence specifications
- Program-status messages, to identify various stages of the job for you
- Action messages (accompanied by a halt), to identify circumstances requiring attention before you can continue the job

Column 27 indicates which of the preceding information you want the program to print during a job:

Col. 27 Entry	Program Prints
0 or blank	Sequence specifications Diagnostic messages Program-status messages Action messages
1	Program-status messages Action messages
2	Action messages only
3	None of above

### Column 28 (Output Option for Tag Along Sorts)

Column 28 applies to tag along sort (SORTR or SORTRS) jobs only. It indicates whether or not you want the program to drop control fields from output records after the records are sorted. A blank in column 28 means keep the control fields; X means drop them.

### Considerations for Dropping Control Fields

Control fields are normally dropped if you are using opposite control fields or an alternate collating sequence. In these two cases, the program changes the control information (during the sorting process) in such a way that it will be meaningless to you.

### Using Fields as Both Control and Data Fields

If you are using opposite control fields or an alternate collating sequence and you want to keep the control information in a meaningful form in the output records, describe the fields twice: once as control fields and once as data fields. Data fields are not involved in the sorting process and are not changed by the program.

### Columns 29-32 (Output Record Length for Tag Along Sorts)

Columns 29-32 apply to tag along sort (SORTR or SORTRS) jobs only. The entry in these columns tells the program the length of records in the final sorted file.

If you do not drop control fields, the length includes both control and data fields. If you drop control fields, the length includes only data fields. In either case, the sum of the control fields and the data fields must not exceed the maximum work record length limits listed in Appendix E.

# Calculating Output Record Length When Dropping Control Fields

For *each* type of record, total the lengths of all the data fields you are including in the job. Select the largest total and enter this number in columns 29-32.

### Calculating Output Record Length When Not Dropping Control Fields

For *each* type of record, total the lengths of the data fields. Select the largest total, add this total to the number in columns 13-17, and put the sum in columns 29-32. (The sum must not exceed the maximum work record length limits listed in Appendix E.)

### **Column 34 (Nonverify Option)**

Column 34 applies to all disk sort runs except those that contain a work file statement for a 3340 disk file on Model 15 only. When a 3340 file (D1, D2, D3, D4) on Model 15 only is used as the work file, the verify option is taken from the OCL FILE statement and column 34 of the sort header record is ignored. Otherwise, if an N is placed in this column of the disk sort header statement, none of the data written on the work file will be verified. This results in an improvement in performance (see Appendix D. Timing Considerations).

*Note:* If you use the nonverify option when your output file is to overlay the input file, the input file might be destroyed if a terminal error occurs before end of job. Therefore, if the input file cannot be easily recreated, you should have a duplicate copy for backup. The input file can be destroyed under the same circumstances whether the nonverify option is used or not. However, the chance is greater when using the nonverify option. Columns 37-38 (Storage Size) – CCP/Disk Sort Model 15 5704-SM7 and 5799-ATH

You designate the required storage size, in multiples of 2K, from 12 to 48 for execution of the object module. The default is 12.

Column 39 (Record Length Indicator) – CCP/Disk Sort Only

Models 4, 8, 10, 12, 15A, 15B, and 15C

R This code indicates that a record length exists in columns 40-43.

Model 15 with Program Number 5704-SM7 Only

- C Indicates task chaining and that a record length exists in columns 40-43.
- R Indicates that a record length exists in columns 40-43.

#### Columns 40-43 (Record Length) – CCP/Disk Sort Only

You designate the input file record length, right justified.

*Note:* If a user comment currently exists, you must fit it into columns 44-72, or remove it.

Columns 40-72 (Job Description) or Columns 44-72 (Job Description – CCP/Disk Sort Only)

This field is for your comments. You can use any System/3 characters you want in these columns. If the program prints specification lines (the column 27 entry is a zero or blank), the comments you include in these columns are printed. Comments have no effect on the program.

#### Columns 75-80 (Program Identification/Program Name)

Disk Sort

For disk sort, the program identification is only used for user reference. It has no program function.

### CCP/Disk Sort

For CCP/Disk Sort, the program name does provide a program function. This field contains the name given to the object program. This is the name that you enter from the terminal to invoke the sort. The entry can be:

- A valid program name. The first character must be alphabetic, but cannot be a #, \$, or @ character. The remaining characters must be alphameric with no embedded blanks or special characters.
- 2. Blank. The default is SRTOBJ.

*Note:* DIR, ALL, and SYSTEM are reserved names and must not be used as program names.

Record type specifications tell disk sort which of the records in a file you want to sort. Remember, if you want to sort all the records in a file, and they all have the same format, you do not have to fill out record type specifications.

### **COLUMN SUMMARY**

Columns	Entries	Explanation
1-2	00-99	Page number
3-5	01x-06x	Line number (you can leave column 5 blank, or enter any value to keep the specifications in ascending order)
6		Include line
1	0	Omit line
7	А	<i>And</i> line (these specifications continue the definition of the record described on the previous line)
	0	<i>Or</i> line (these specifications define a different type of record than the one on the previous line)
	Blank	First line of a set of I or O record type lines
	*	Comment line
8	С	Use both zone and digit portions of characters
	Z	Use only zone portion of 1-character field
	D	Use only digit portion of characters
	Р	Signed packed decimal data
	U	Signed unpacked decimal data
9-12	1-4096	The input record position in which the factor 1 field begins (blank if field is only one position long)
13-16	1-4096	The input record position in which the factor 1 field ends
17-18	EQ NE LT GT LE GE	Factor 1 must equal factor 2 Factor 1 must not equal factor 2 Factor 1 must be less than factor 2 Factor 1 must be greater than factor 2 Factor 1 must be less than or equal to factor 2 Factor 1 must be greater than or equal to factor 2
19	С	Factor 2 is a constant
	F	Factor 2 is another field in the same input record
20-23	1-4096	The input record position in which the factor 2 field begins (blank if field is only one position long)
24-27	1-4096	The input record position in which the factor 2 field ends
20-39	Any System/3 characters	The factor 2 constant
40-72	Any System/3 characters	Comments

Columns that must be filled in

### **COLUMN DESCRIPTIONS**

### Columns 1-2 (Page Number) and 3-5 (Line Number)

Page number (columns 1-2) and line number (columns 3-5) form a 5-digit sequence number. As the program reads sequence specifications, it checks the sequence numbers to make sure they are not in descending order. If the numbers are in descending order (for example, if page 02 specifications come before page 01 specifications) and specifications are being printed, the program will print a warning (the letter S) next to the line (the S stands for sequence error). After a warning is issued, the program continues reading the rest of the specification lines, then halts and waits for further instructions from the operator. The operator can either continue or end the job.

Because page number applies to all lines on a page, columns 1-2 appear only once, in the upper right corner of the page. Number the pages in ascending order.

Record type line numbers are 01 through 06. The numbers in columns 3 and 4 are preprinted on the coding sheet. You can leave column 5 blank or enter any value to keep your specifications in ascending order. If you have more than six record type lines, use another coding sheet and start at line 01.

#### **Out-of-Sequence** Lines

Use column 5 when you want to insert a specification without renumbering the other specifications. For example, to insert a specification line between lines 01010 and 01020, you can number it 01015, code it, and then continue to fill out the rest of the sheet.

Be sure any lines that are out of sequence on your coding sheet are clearly marked. You can do this by writing a note in the margin of the page with an arrow pointing to where the insert belongs (see *Sample Job 3*).

#### Column 6 (Line Type)

Column 6 identifies the type of record type line. An I in this column stands for either an include or an include-all line; an O stands for an omit line.

#### Include Line

Include lines identify records you want the program to sort by describing particular record fields.

### Include-All Line

Include-all is a special form of include line; it has no record description (columns 7-39 are blank). It tells the program to sort all the records that have not been described by any preceding include or omit line for the job. Records referred to in this manner must have the same field specifications.

*Note:* Only one include-all line can be used per job. If used, it must be the last record type line for that job.

### Summary: Include Lines

If the type of sort job you are running requires you to code record type lines, you must use include or include-all lines to describe the records you want sorted. Records not described in include lines will not be sorted.

#### Omit Line

Omit lines identify records you do *not* want the program to sort. Omit lines are not required but can be helpful when you have many types of records you want the program to use and just a few you want omitted. Omit lines are normally followed by an include-all line, telling the program to sort all the records that are not described by omit lines. Sets

There are two types of sets: include sets and omit sets. An include set identifies one or more record types you want to include in your sort job. An omit set identifies one or more record types you want to omit from your sort job. (The records in any record type always have at least one characteristic in common – such as an X in position 5.)

Here are four rules to remember when you are using include and omit sets:

- 1. All include sets must end with a field description line.
- 2. Omit sets never have field description lines.
- 3. Every omit set must be followed by an include set.
- 4. The last set must be an include set.

There are five types of include sets and three types of omit sets.

Туре	Col. 6	Col. 7	Explanation
,	H, F, or O		Header line, field description line, or omit line
Include AND lines	1	b A	Record type lines: New record type indicated by blank in column 7. Lines that describe the same record type (as the previous line) have an A in column 7.
	F		Field description line(s)
	H, F, or O		Header line, field description line, or omit line
Include OR lines	1. 1.	ъ О	Record type lines: New record type indicated by blank in column 7. Lines that describe different record types (than the previous line) have an O in column 7.
	F	4.1	Field description line(s)
	H, F, or O		Header line, field description line, or omit line
Include AND and OR lines	1	ю О	Record type lines: New record type indicated by blank in column 7. This line designates a record type which is different than but has the same field description lines as the record type described in the previou
		A	line(s). This line continues the same record type of a previous line or lines. Th record type can be continued (IA), or another record type can be started (IO), provided all record types have the same field description lines. Record types with different field lines would have to start a ne include set.
	F		Field description line(s) for either A or O record types
Include	н		Header line
only one record			No record type lines
type (implied include- all)	F		Field description line(s)
	H, F, or O		Header line, field description line, or omit line
Include- all	1		Record type line: Tells program to sort all the records that have not been described by any preceding include and omit lines. Records referred to i this manner must have identical field specifications.
	F		Field description line(s)

<sup>1</sup> Every include set must end with field description lines. An include set can be followed by another include set, an omit set, or // END.

Note: Records not described in include sets will not be sorted.

### INCLUDE SETS<sup>1</sup>

### **OMIT SETS<sup>1</sup>**

Туре	Col. 6	Col. 7	Explanation
Omit AND lines (one record type)	H or F O O	Ь	Header line or field description line (last line of include set) New record type indicated by blank in column 7. Lines that describe the same record type (as the previous line) have an A in column 7.
Omit OR lines (different record types)	H or F O O	о Ю	Header line or field description line (last line of include set) New record type indicated by blank in column 7. Lines that describe different record types (than the previous line) have an O in column 7.
Omit AND and OR lines (different record types)	H or F O O	ь А О	Header line or field description line (last line of include set) New record type indicated by blank in column 7. Lines that describe the same record type (as the previous line) have an A in column 7. Lines that describe different record types
There are no field description			Lines that describe different record types (than the previous lines) have an O in column 7. Each omit set must be followed by an include or an include-all

# Guide to Using Include and Omit Sets

When to Use Include Sets: If you want to sort only a few records in a file, use an include set for each type of record you want to sort.

When to Use Omit Sets: If you want to sort all but a few records in a file, use omit sets followed by either an include set for each type of record you want to sort or an include-all set.

*Mixing Include and Omit Sets:* You can mix include and omit sets; but because disk sort processes the sets in the order they are coded, you must be particularly careful when you do this. For example, if you wanted to omit all records with a 2 in position 10 but sort those with a 2 in positions 10 and 15, you would have to specify the include set before the omit set. If you specified the omit set first, all the records you want sorted would be omitted from the job.

# **Column 7 (Continuation or Comments)**

Column 7 indicates the line's relationship to the preceding line.

Col. 7 Entry	Explanation
Blank	This line is the first of a set of include or omit lines. (The type of set is indi- cated by the column 6 entry: I for include — O for omit.)
А	The line is a continuation of the pre- ceding line. The A stands for AND.
0	The line applies to a different record type than the preceding line, but the control field specifications for both are the same. The O stands for OR.
* 	This line is a comment line. Comment lines do not affect the program in any way. Their only purpose is to help you remember what you were doing in a certain section of coding. (Comments are printed only if column 27 of the header line contains a zero or a blank.)

# Column 8 (C/Z/D/P/U)

Your column 8 entry tells disk sort how to interpret data in the factor 1 and factor 2 fields during compare operations. When the fields contain alphameric data, a C, Z, or D entry tells disk sort what portions of the characters to use. When the fields contain signed numeric data, a P or U entry tells disk sort whether the data is packed or unpacked.

	Col. 8 Entry	Compare Operations	Maximum Field Length <sup>1</sup>
	С	Use both zone and digit portions of the characters	256 characters
Alphameric data	Z	Use only the zone portion of the character	1 character
	D	Use only the digit portion of the characters	16 characters
Signed (	P <sup>2</sup>	Numeric data is packed	8 bytes or 16 digits
numeric data	U <sup>2</sup>	Numeric data is unpacked	16 digits
X	<sup>2</sup> Do not use a type specifica	or 1 and factor 2 fields packed or unpacked factor 1 in an ation (P or U in column 8) if you s ience (S in column 26 of header li	specify an alternate

30

### Significance of the Column 8 Entry

You use record type specifications to tell the disk sort program which records you want to sort. You do this by instructing disk sort to test each record by comparing the data in a specific field against a constant or against the data in another field in the same record. The data you are comparing is the factor 1 field; the data you are comparing it against (a constant or the contents of another field in the same record) is the factor 2 field. The result of the comparisons determines whether or not that record will be sorted. Since the disk sort program sees your data as nothing more than a series of electronic bits, you must tell the program how to interpret the data:

- If the data is alphameric, what part of the characters to use
- If the data is signed numeric, whether it is in packed or unpacked format

### Interpreting System/3 Data

Each System/3 EBCDIC character has two parts: a zone portion and a digit portion. Some characters have identical zone portions; some have identical digit portions. No two characters have identical zone and digit portions.

System /2 Obayaster	How It Looks inside the Computer		
System/3 Character	Zone Portion	Digit Portion	
*	0101	1100	
1	1111	0001	
2	1111	0010	
3	1111	0011	
к	1101	0010	
?	0110	1111	
Р	1101	0111	
blank	0100	00001	
0	1111	00001	
<sup>1</sup> Notice that the digit portion of a zero and blank look exactly the same.			

If you instruct disk sort to use only the digit portions of characters (by putting a D in column 8), characters with identical digit portions will look alike and compare as equal. Likewise, if you instruct disk sort to use only the zone portion of characters (by putting a Z in column 8) characters with identical zone portions will look alike and compare as equal. Thus your column 8 entry is critical in ensuring that your compare operations produce the results you intend.

Suppose, for example, that you want only those records with a 2 in column 15 and a 2 in column 50. If you put a D in column 8, you will get the records you want: the ones with a 2 in column 15 and a 2 in column 50. But you will also get a lot of records you do not want (several characters have the same digit portion as a 2). To get *only* the records with a 2 in column 15 and a 2 in column 50 you would have to put a C in column 8. The C tells disk sort to use both the zone and digit portions of characters in its compare operations, and no other System/3 character has the same zone and digit portion as a 2.

*Note:* The leftmost bit of each byte of ASCII data that is not converted to EBCDIC is set to zeros.

### Alphameric Data

When the factor 1 and factor 2 fields contain alphameric data, the column 8 entry must specify one of the following:

- The zone and digit portions of the characters (C entry)
- Only the zone portion of the character (Z entry)
- Only the digit portion of the character (D entry)

# Numeric Data

When the factor 1 and factor 2 fields contain numeric data, the column 8 entry must answer two questions:

1. Are the numbers signed or unsigned?

2. Are the numbers packed or unpacked?

Format Numeric		Col. 8 Entry	Definition	Considerations <sup>1</sup>
Unsigne	d	D	Numbęr does not have a sign.	Absolute values of the numbers are used. If a number has a sign, it is ignored. For example, -3 would be considered equal to +3.
	Packed	<b>P</b>	Number always carries a sign. When the number is placed in core storage it has a digit portion only.	The sign controls the comparison. For example, -3 is less than 0 and +5 is more than -6.
Signed	Unpacked	U	Number always carries a sign. When the number is placed in core storage, it has both a zone and digit portion	The sign controls the comparison. For example, –3 is less than 0 and +5 is more than –6.
<sup>1</sup> Before	comparing nu	meric data	a, disk sort converts a	ny leading blanks to zeros.

*Signed Numbers:* Signed numbers can be either positive or negative. The sign of a number is indicated by a 4-bit binary code.

*Packed and Unpacked Numbers:* An unpacked digit takes up eight bits; a packed digit takes up four bits.


Sign	Binary Code	
+	1111 <sup>1</sup>	
	1010	
	1100	
	1110	
-	1101	
	1011	

<sup>1</sup>Standard form. Disk sort accepts all four forms of the plus sign. Before sorting the file, however, the program converts all plus signs to the standard form. If you print a core dump, the plus sign will always be expressed as a hex F.

Packed Digits		
Digit	Digit Binary Form	
0	0000	
1	0001	
2	0010	
3	0011	
4	0100	
5	0101	
6	0110	
7	0111	
8	1000	
9	1001	

Unpacked Digits		
Digit	Binary Form	
0	1111	0000
1	1111	0001
2	1111	0010
3	1111	0011
4	1111	0100
5	1111	0101
6	1111	0110
7	1111	0111
8	1111	1000
9	1111	1001
	$\sim$	$\sim$
	Zone	Digit
	Portion	Portion

In unpacked numbers, the 4-bit sign code replaces the zone portion of the last digit in the number. In packed numbers the sign code takes up the last four bits of the number.



# Columns 9-16 (Factor 1 Location)

Factor 1 fields identify your records. (If all your inventory records contain an 1 in column 2, for example, column 2 is a factor 1 field.) Disk sort identifies records you want sorted by comparing factor 1 fields against constants or against other fields in the same record. Columns 9-16 identify the locations of the factor 1 fields in the records. If there is more than one factor 1 field for the records you are describing, you must:

- Describe each field in a separate record type line.
- Put an A in column 7 of every line (except the first) to tell disk sort that all the lines apply to the same record type.

Columns 9-12 (from) identify where the factor 1 field begins in the record. Columns 13-16 (to) identify where the field ends.

### Length of Factor 1 Fields

A factor 1 field can contain anywhere from 1 to 256 characters. No factor 1 field, however, can be longer than the length of the records you are working with. (For example, when you are working with 96-column records, the longest possible factor 1 field you can have is a 96-character field.) The length of factor 1 fields is also controlled by the column 8 entry.

Col. 8 Entry	Maximum Factor 1 Field Length	
С	256 characters <sup>1</sup>	
Z	1 character	
D	16 characters	
Р	8 characters <sup>2</sup>	
U	16 characters	

<sup>1</sup>When factor 2 is a constant, the length of the factor 1 field must not exceed 20 characters (see *Columns 20-39* for more information).


<sup>2</sup>Because the factor 1 field is packed, the field can actually represent 15 decimal digits and a sign.

#### Coding Rules

Entries must be right-justified: the from entry must end in column 12; the to entry must end in column 16.

To describe factor 1 fields that are only one character long, leave columns 9-12 (from) blank and enter the number of the record position that contains the character in columns 13-16 (to).

For example, here is the entry you would make to describe the position of a factor 1 field which consists of an I in column 2.



### Columns 17-18 (Relation)

The program identifies records you want to sort by comparing the factor 1 field (columns 9-16) against either a constant (columns 20-39) or another field (columns 20-27) in the same record. The constant or other field is called factor 2. Columns 17-18 tell the program what the results of the comparison must be. (If alternate collating sequence is used, both factor 1 and factor 2 are modified before the comparison is made.)

Col. 17-18 Entry	Meaning
EQ <sup>1</sup>	Factor 1 must equal factor 2.
NE <sup>1</sup>	Factor 1 must not equal factor 2.
LT	Factor 1 must be less than factor 2.
GT	Factor 1 must be greater than factor 2.
LE	Factor 1 must be less than or equal to factor 2.
GE	Factor 1 must be greater than or equal to factor 2.
characte	want the program to compare zone portions of rs (Z in column 8), EQ and NE are the only ou can use.

### Column 19 (Field or Constant)

The program identifies records you want to sort by comparing the factor 1 field (columns 9-16) with a constant, or another field in the same record. The constant or other field is called factor 2. Column 19 tells the program whether factor 2 is a constant or another field. C in column 19 means factor 2 is a constant; F means factor 2 is a field.

When you put a C in column 19, you use columns 20-39 for the constant. When you put an F in column 19, you use columns 20-27 to identify the location of the factor 2 field in the records.

*Note:* The K shown in column 19 on the sequence specification sheet is not used for System/3 disk sort.

#### Columns 20-27 (Factor 2 Field)

The factor 2 field must be the same length as the factor 1 field. It also must be in the same record as the factor 1 field.

Columns 20-27 are used to record the location of the factor 2 field. Columns 20-23 (from) identify the starting position of the field; columns 24-27 (to) identify where the field ends.

*Note:* The keyword parameter shown for columns 20-25 on the sequence specification sheet is not used for System/3 disk sort.

### Coding Rules


Entries must be right-justified: the from entry must end in column 23; the to entry must end in column 27.


To describe fields that are only one character long, leave columns 20-23 (from) blank, and enter the number of the record position that contains the character in columns 24-27 (to).

# Columns 20-39 (Factor 2 Constant)

When factor 2 is a constant, you use columns 20-39 to write in the constant you want to use. The constant can be any arrangement of System/3 characters.

The constant must be the same length as the factor 1 field. For example, if you have a 4-position factor 1 field, your constant field must take up four positions. If your constant is the number 6, you would put the 6 in column 23, and either leave columns 20, 21, and 22 blank or fill them with zeros.





If the factor 1 field contains a packed number, the length of the constant (including the sign) must be twice the length of the factor 1 field. The reason for this is that factor 1 data is in packed form, and the constant you are writing in is in unpacked form.

# Alphameric Constants (Column 8 Entry is C, Z, or D)

The constant must be the same length as the factor 1 field and must always begin in column 20.

#### Numeric Constants (Column 8 Entry is P, U, or D)

*Format:* Numeric constants must be right-justified within the field length specified in factor 1 (within twice the field length if factor 1 is a packed number). For example, assume that factor 1 defines a 6-position field in the input record, and that factor 2 is the numeric constant 123. To rightjustify the constant within six positions, you would have to put the constant in columns 23, 24, and 25. Leading zeros are not required. To disk sort, blanks and zeros look the same. In the example above, columns 20-25 could contain either 000123 or bbb123 (with b representing a blank).

Signed Constants: If factor 1 is a packed number, the last character in the constant must be its sign (+ or -). If factor 1 is an unpacked number and the constant is a negative number, the last digit in the constant must be a character that indicates both the numeric value of the last digit and the negative sign for the entire constant.


If Last Digit	Character that	How the Number Looks inside the Computer	
in Constant is	You Code	Zone Portion <sup>1</sup>	Digit Portion <sup>2</sup>
0	– (minus code) <sup>3</sup>	0110	0000
1	J	1101	0001
2	κ	1101	0010
3	L	1101	0011
4	M	1101	0100
5	N	1101	0101
6	0	1101	0110
7	P	1101	0111
8	Q	1101	1000
9	R	1101	1001

<sup>1</sup>The zone portion indicates the negative sign of the entire number.

<sup>2</sup>The digit portion indicates the numeric value of the last digit in the number.

<sup>3</sup>If your system input device is a system card device, you can punch a zero and minus in the same card column.

For example, here is the entry you would make to sort records which have a packed negative 1 (-1) in positions 1 and 2, an unpacked negative 24 (-24) in positions 5-8, and an unpacked negative 10 (-10) in positions 11-16:



# Columns 40-72 (Comments)

Columns 40-72 are for your comments. If you have instructed disk sort to print sequence specifications (column 27 of the header line is either blank or contains a zero) the comments will be printed along with your sequence specifications. The comments have no effect on the program's operation.

Many programmers like to use columns 40-47 to write the names of the records described in the record type specifications. This is why columns 40-47 are enclosed in dotted lines on the coding sheet. Field description specifications tell disk sort how to arrange (format) records in the output file.

# COLUMN SUMMARY

Columns	Contents	Explanation
1-2	00-99	Page number
3-5	07x-14x	Line number (you can leave column 5 blank, or enter any value to keep the specifications in ascending order).
6	F	Field specification line
7	N	Normal control field
	0	Opposite control field
	F	Forced control field
	D	Data field
	S	Summary data field
	*	Comment line
	P	Signed packed decimal data
	U	Signed unpacked decimal data
8 C_	С_	Use both zone and digit portions of characters in the field
	Z	Use only zone portion of 1-character field
	D	Use only digit portion of characters in the field
	V	Force a data character into the data field
9-12	1-4096	Starting position of field in the record (blank if field is one character long)
13-16	1-4096	End position of field in the record
17	Any System/3 character	Forced control fields only (the character you want the program to change)
18	Any System/3 character	Forced control fields only (the character you want to substitute)
19	Blank	Forced control field line is not a continuation of the preceding line
	Any character other than blank	Forced control field line is a continuation of the pre- ceding line
20-22	1-16	Summary tag along sort only (overflow field length entry
23-39	Not used	Not used
40-72	Any System/3 characters	Comments

Columns that must be filled in for all sort jobs

Columns that must be filled in when forced control fields are used

# **COLUMN DESCRIPTION**

### Columns 1-2 (Page Number) and 3-5 (Line Number)

Page number (columns 1-2) and line number (columns 3-5) form a 5-digit sequence number. As the program reads sequence specifications, it checks the sequence numbers to make sure they are not in descending order. If the numbers are in descending order (for example, if page 02 specifications come before page 01 specifications) and specifications are being printed, the program will print a warning next to the line. After a warning is issued (the letter S), the program reads the rest of the specification lines and then halts and waits for further instructions from the operator. The operator can either continue or end the job.

Because page number applies to all lines on the page, columns 1-2 appear only once, in the upper right corner of the page. Number the pages in ascending order.

Here is the recommended procedure for field description line numbers. Field line numbers are 07 through 14. The numbers in columns 3 and 4 are preprinted on the coding sheet. You can leave column 5 blank, or enter any value to keep your specifications in ascending order. If you have more than eight field lines, use another coding sheet and start at line 07.

Use column 5 when you want to insert a specification line without renumbering the other lines. For example, to insert a specification line between lines 01070 and 01080, you can number it 01075, code it, and then continue to fill out the rest of the sheet.

Be sure any lines that are out of sequence are clearly marked. You can do this by writing a note in the margin of the page with an arrow pointing to where the insert belongs (see Sample Job 3).

# Column 6 (Line Type)

Column 6 contains a preprinted F, identifying the line as a field line. For addrout sorts (SORTA), field lines describe control fields the program uses to sort record addresses. For tag along sorts (SORTR) and summary tag along sorts (SORTRS), field lines describe the fields that the program uses to create the records in the sorted output file. The fields can be either control fields (used to sort the records) or actual data fields. In addition, for summary tag along sorts, field lines describe the fields that the program summarizes (adds together).

### **Column 7 (Field Type or Comments)**

Your column 7 entry tells disk sort whether you are describing a control field, data field, or comment line. If you are describing a control field, the column 7 entry indicates how the field is to be used. See *Columns 7-8* to find the ways you can combine this entry with the column 8 entry.

1					
Col. 7 Entry	Tells Program				
D	This is a data field <sup>1</sup>				
*	This is a comment line.				
N	This is a normal control field. Sort this field so that the data from the field is in the se- quence specified in column 18 of the header line.				
0	This is an opposite control field. Sort this field so that the data from the field is in the sequence opposite that specified in column 18 of the header line.				
F	This is a forced control field. Change the con- trol field according to the entries in columns 9-19.				
S	This is a summary data field <sup>2</sup>				
only. (If y	<sup>1</sup> Use this entry for tag along (SORTR, SORTRS) sorts only. (If you use a D entry during an addrout sort, the line will be treated like a comment line.)				
(If you us will be tre entry duri	ntry for summary tag along (SORTRS) only. e an S entry during an addrout sort, the line ated like a comment line. If you use an S ing a tag along sort, the fields will be normal data fields).				

### Data Fields (D in Column 7)

Data fields apply to tag along (SORTR, SORTRS) sort jobs only. They are fields you want the program to include in the sorted records, but which you do not want the program to use in sorting the records. Within each include set (include and field description lines), control field lines must be placed before data field lines.

When your file has more than one type of record:

- The number of data fields does not have to be the same for all record types.
- The total lengths of all the data fields do not have to be the same for all record types. Disk sort places blanks to the right of shorter data fields so that all total lengths are equal.

# Comment Lines (\* in Column 7)

Comment lines help document the program. They do not affect the program's operation. You can code comment lines anywhere in the sequence specifications; however, comments will be printed only if column 27 of the header line contains a zero or blank.

# Control Fields (N, O, or F in Column 7)

There is no limit to the number of control fields allowed, however, the total length of all the control fields must be from 1 to 256 bytes long.

When your file has more than one type of record:

- The number of control fields does not have to be the same for all record types.
- The total *lengths* of the control fields do not have to be the same for all record types.

When records with duplicate control fields (records with all control fields equal) are sorted, their order as output is unpredictable.

Normal and Opposite Control Fields (N or O in Column 7): These control fields are fields the program uses to sort records or record addresses. They are fields in your input records. However, you can define 1-character control fields that are not in the records by using an unconditional force. (See Forced Control Fields.)


Forced Control Fields (F in Column 7): There are three types of forced control fields:

- Conditional
- Force-all
- Unconditional


Forced control fields affect the work and output records only. (It is important to remember that disk sort never changes your input records.)

See Column 17, Column 18 and Column 19 for information on how to fill out the field description specifications when you are using forced control fields. A conditional force occurs *only* if a control field in the input record contains a particular entry. Suppose, for example, that you want to sort a file of records, each of which has a 1-position control field. If the character in the control field is an X, you want to replace it with an A before you sort the records. To do this, you would use a conditional force. Your conditional force field would tell disk sort:

Build a work record from the input record:



If the control field contains an X, change it to an A:



Force-all is a special type of conditional force. Force-all occurs only when a control field in an input record *does not* contain a particular entry. Suppose, for example, that you want to sort a file of records, each of which has a 1-position control field. If the character in the control field is *not* a C, you want to put an X in the field before you sort the records. To do this, you would use a force-all line to force the X into the control field.

A force-all line follows a series of conditional force lines. For example, you may want to tell disk sort:

- If the control field contains a C, replace it with a 1.
- If the control field contains an F, replace it with a 2.
- If the control field contains a \$, replace it with a 3.
- If the control field does *not* contain a C, an F, or a \$, put an X in the control field. (You are *forcing* out *all* other possible entries by using a force-all line.)

An unconditional force does not depend on entries in the input records. If, for example, you want to put a dollar sign (\$) in the first position of every output record, you would use an unconditional force. Your unconditional forced control field would tell disk sort to put a dollar sign in the first available control field position of the work record.



**Control fields** Data portion portion

Any other control fields will go after the dollar sign. Assume the input records are in this format:

Data	Control field A	Data	Control field B	Data

The work record will then look like this:

\$	Control field A	Control field B	Data
the second second second		and the second	the second se

See Column 19 for actual coding examples of forced control fields.

### Summary Data Fields (S in Column 7)

An S in column 7 of the field description specifications defines a summary data field. You can define summary fields for all three types of sort jobs, but the fields will be summarized (added together) only in summary sorts. In tag along sorts (SORTR), summary fields will be treated as normal data fields. In addrout sorts (SORTA), summary fields will be treated as comments.

In a summary sort, the summary data fields in the work and output records for individual record types must always be in the same position. The fields do not have to be in the same position in the input records. (See messages SD278 and SD280.)

No more than 24 fields can be summarized for each record type.

The first include set that contains summary specifications defines the summary format for all included records. It is recommended that all include sets contain summary specifications. If an include set does not contain summary specifications, the data specification should align the data for summarization.

If no summary specifications are given for a SORTRS type sort, the output file consists of records with unlike control fields as specified in the field statement. Disk sort deletes all records with common control fields. Only one copy of each is retained.

### Column 8 (C/Z/D/P/U/V)

Your column 8 entry indicates what portion of the input record's characters you want disk sort to use in building and sorting the work records. The column 8 entry is critical in assuring that the sort produces the results you intend. See Columns 7-8 to find the ways you can combine this entry with the column 7 entry.

Col. 8 Entry	Character Portion Used	Maximum Field Length		
С	Use both zone and digit portions of the characters	256 characters		
Z	Use only the zone portion of the character	1 character		
D	Use only the digit portion of the characters	16 characters		
Р	The characters are signed, packed decimal numbers <sup>1</sup>	8 bytes or 15 digits and sign		
U	The characters are signed, unpacked decimal numbers <sup>1</sup>	16 digits		
V	Force a data character into the data field	1 character		
<sup>1</sup> Note that -3 is less than 0 and +5 is greater than -6.				

Suppose, for example, you have a 1-character control field in your input records which can be either an \*, 1, 2, or 3. The zone and digit portion of each character is:

Character	Zone	Digit
*	0101	1100
1	1111	0001
2	1111	0010
3	1111	0011

If you want the records sorted into ascending order using the digit portion of the control field characters (by putting a D in column 8), they will be in this order:

1

2 3

If you want the records sorted into ascending order using both the zone and digit portions (by putting a C in column 8), they will be in this order:

- \* 1 2
- 3

Suppose you placed a Z in column 8 and wanted the records sorted into ascending order. You can then be sure that the records with an \* control field will precede the records with a 1, 2, or 3 control field. Since 1, 2, and 3 have identical zone portions, records with any of these numbers as a control field will not be in any special order after the sort.

If you want to force characters into your data field, place a V in column 8 and specify the character to be forced in column 18. That character will be placed in the first available data field position of the work record.

As you can see, your column 8 entry can drastically affect your sorted file.

Do not confuse this column 8 entry with the column 8 entry on the record type specifications. Column 8 of the field type specifications tells disk sort what portion of a character to use to sort the records. The column 8 entry on the record type specifications helps select which records you want to be sorted.

# **Opposite Control Fields**

If you want to sort records so that some control fields are in ascending order and other control fields are in descending order, use opposite control fields. An opposite control field is sorted in ascending order (if you specify descending order on the header line), or in descending order (if you specify ascending order on the header line). If your file contains different record types, all of which have an opposite control field in the same record position, your column 8 entries for these control fields must be one of the following:

- All Ds
- All Cs
- All Zs
- Any combination of Cs and Zs

With any other combination of entries (for example, Ds and Cs), you will not be able to predict the results of the sort.

When you use opposite control fields, disk sort changes them in building the work record. Therefore, you usually drop this meaningless control field information (by coding an X in column 28 on the header line) for tag along or summary sorts. If the opposite control fields are all Ds, you do not need to drop the control field. If you wish to retain the original control field data in the output record, repeat the information as a data field.

## Packed or Unpacked Control Fields (Normal or Opposite)

If you specify packed or unpacked control fields, disk sort changes the control fields while building the work record. Therefore, you must drop the control field information by coding an X in column 28 on the header line. If you wish to retain the original control field data in the output record, repeat the information as a data field.

### Forced Control Fields

Here are a few rules to remember when you are using forced control fields:

- You can have only one character in your forced control field.
- You can indicate either a conditional or an unconditional force.
- A force-all line must be preceded by a conditional force line.
- You define a forced control field by placing an F in column 7 of the field specifications.

See Columns 9-16, Column 17, Column 18, and Column 19 for further information on how to complete the field specifications.

Using Control Fields to Sequence Information in the Sorted Records

The order in which you describe control fields in the field specification lines determines the sequence of the records (tag along sort) or the record addresses (addrout sort) in the sorted file. Suppose each record in your file that is sorted in ascending order (A in column 18 of the header line) has a normal control field in positions 1-2 and an opposite control field in positions 5-7. Each record represents one customer's order for a separate item. The part number is in position 1-2; the number of parts ordered is in positions 5-7. Your unsorted file might look like this:


	In 1	· .	recor 3 4	d po 5	osit 6	ion 7	
0	1	7		1	2	6	
1	3	4		5	1	2	
2	1	7		1	2	1	
3	1	5			9	6	
4	3	4			1	8	
5	1	7			2	0	
6	3	4		2	5	0	
Input record number	Par	t mbe	er _		mb Jere		

You can use the first control field to sort the records in ascending order according to the part number. You can then use the second control field to sort the number of parts ordered in descending order within each group of parts. Therefore, you want your sorted file to look like this:

Output record position					
	1	2	3	4	5
0	1	5		9	6
1	1	7	1	2	6
2	1	7	1	2	1
3	1	7		2	0
4	3	4	5	1	2
5	3	4	2	5	0
6	3	4		1	8
<u> </u>	_	~	_	~~	5.

Output Part Number record number ordered number

# Include these field specifications to do the preceding sort:



Notice that the information occupies different positions in the input and output records. The record positions change when the control fields and data fields are moved from the input to the work to the output files. Since an opposite control field is specified, all the control fields in the input record are dropped (columns 1-2 and 5-7). To save the control fields, specify them as data (see example).

#### Columns 7-8

Here are all the possible combinations for columns 7 and 8:

		Maximum		
Col. 7	Col. 8	Field Length		
N or O	С	256		
	Z	1		
	D	16		
	Р	8		
. :	υ	16		
F	C1	1		
	Z1	1		
12	D1	1		
D	С	256		
	Z	1		
	D	16		
	Р	8		
	U	16		
	v	1		
S	С	256		
	z	1		
	D	16		
	P	8		
	U	16		
·	V	1		
*		Does not apply		
(comment line)				
<sup>1</sup> For an	unconditio	onal force and a		
force-al	l line, colu	mn 8 must con-		
tain a C	•			


See *Column 7* and *Column 8* for detailed discussions of each entry.

# **Columns 9-16 (Field Location)**


Columns 9-16 identify the input record positions that contain the record fields. Columns 9-12 (from) identify the starting position of a field; columns 13-16 (to) identify the position in which the field ends.

The order in which you describe the fields in the field description specifications determines the order they will be in in the sorted output records.


For example, suppose you have an input record that looks like this:



However, you want your sorted output record to look like this:




Assuming that you want to sort the records by item number, here is how you would fill out the field description specifications:



44

As another example, if you want the 1-character field in position 20 of your input record to be in the first position of the sorted output record, you would describe the field in the first line of your field description specifications. In this example, the primary control field for the output file is determined by position 20 of the record:



# Field Length

The length of the field depends on the column 8 entry.

Col. 8 Entry	Maximum Field Length
С	256 characters
Z	1 character
Р	8 characters
U	16 characters
D	16 characters
V	1 character

#### Coding Rules

Entries must be right-justified. The from entry must end in column 12; the to entry must end in column 16.

To describe fields that are only one character long, leave columns 9-12 (from) blank, and enter the number of the record position that contains the character in columns 13-16 (to).

## **Column 17 (Conditionally Forced Character)**

See *Column 7* for general discussion of forced control fields. You make an entry in column 17 only when you want to use a conditional force. (For example, if you want to put an \* in a control field only if the present entry is an A.) When you use conditional force, the input record does not change, but the work and output records will contain an \* instead of an A. (See *Column 7* or *Column 18* for more information about conditional force.)

The column 17 entry tells disk sort which character in the control field (defined in columns 13-16) you want to replace. The program checks to see if the control field in the work record contains the character you specified in column 17. If it does, the character in column 18 replaces the control field character.

If a control field can contain any one of several characters and you want to specify a forced character replacement for each one, you must include a column 19 entry in all the forced field lines (except the first). See *Column 19* for instructions.

### **Column 18 (Forced Character)**

See *Column 7* for general discussion of forced control fields. You make an entry in column 18 only when you are using forced control fields to sort your records. The character in column 18 either replaces the control field character you specify in column 17 or adds a new character to the control field.

Remember that the change to the control field does not alter your input record. Remember, too, that you must use forced control characters only with 1-character control fields.

# Defining a Conditional Force Character

- 1. Fill in columns 1-6 as you would for any control field.
- 2. Put an F in column 7.
- 3. Define the position of the control field in the input record in columns 13-16.
- 4. Enter the character you want to replace in column 17.
- 5. Enter the character you want to replace it with in column 18 (you can use any System/3 character in column 18).

### Defining a Force-All Character

- 1. Fill in columns 1-6 as you would for any control field.
- 2. Put an F in column 7.
- 3. Put the character which replaces the control field in column 18.
- 4. Put any System/3 character in column 19. (The character in column 19 tells disk sort that the line is a continuation of the preceding line.)
- 5. Leave columns 9-17 blank.

If you do *not* place a force-all line after conditional force lines and disk sort does *not* find the specified characters in the control field of the input record, disk sort:

- Replaces the control field character with hex FF (if you specified ascending sequence in the header line).
- Replaces the control field character with hex 00 (if you specified descending sequence in the header line).

#### Defining an Unconditional Force Character

- 1. Fill in columns 1-6 as you would for any control field.
- 2. Put an F in column 7.
- 3. Put the character you are forcing in column 18.
- 4. Leave columns 9-17 blank.

Sample Job 4 illustrates the use of conditionally forced characters to group record types.

# Specifying an Overflow Indicator Field

- 1. Fill in columns 1-6 as you would for any control field.
- 2. Put an S in column 7.
- 3. Put a V in column 8.
- 4. Enter a character in column 17 if you do not wish to use an \* as a replacement. If overflow occurs in any summary data field in the record, the initial value of the overflow field will be replaced by the character in column 17.
- 5. Enter a character in column 18. If none of the summary data fields overflow, the overflow field will contain the character specified in column 18.

# Column 19 (Specifying Replacements for More Than One Character)

If a control field in the input record can contain any one of several characters and you want to specify forced character replacements for more than one character, use a separate line to define each possible character and the forced character you want to replace it with.

Note that column 19 is assumed blank for the first field statement of an include set.

# Coding Rules

- 1. Define the control field in columns 13-16.
- 2. Enter the first character you want to replace in column 17.
- 3. Enter the character you want to replace it with in column 18.
- 4. Enter the next character you want to replace in column 17.
- 5. Enter the character you want to replace it with in column 18.
- Enter any character (except blank) in column 19. This tells disk sort the line refers to the same control field in the work record as the preceding line.

Repeat steps 4, 5, and 6 for any other characters to be replaced in that control field.

Note that you can use any System/3 character you want in column 18.

# **Examples of Using Forced Control Fields**


You can use forced control fields to change (add to or replace) a character in a 1-position control field. The following examples represent these types of forced control characters:

- Unconditional force
- Conditional force using only forced control fields

- Conditional force using normal or opposite and forced control fields
- Force-all


# Unconditionally Forced Character

This example illustrates how you can unconditionally place a control field into the work and output records:



# Conditional Force Using Only Forced Control Fields

This example illustrates how control field characters change according to the conditions you specify.




This example also shows how you use column 19 to specify conditional replacements for more than one character. Because continuation lines are used, only one position in the work and output records is defined by the first three lines. If column 19 is left blank, each line would define a new position in the work and output records.

If you are sorting records into ascending order (A in column 18 of the header line), disk sort places hex FF into the work record before you force any characters. If you are sorting records into descending order (D in column 18 of the header line), disk sort places hex 00 into the work record before you force any characters. Therefore, if disk sort does not find an A, B, or C in position 4 of the input record, the hex 00 or FF is left unchanged in the work record.


# Conditional Force Using Normal or Opposite and Forced Control Fields

This example is similar to the previous one since the control field in the input record causes changes in the work and output records. In this case, however, disk sort first moves the control field to the work record (because the first control field is a normal control field) and then changes it if necessary. Notice that any forced character replacements are made *before* the records are sorted.



# Force-All

Suppose your control field can contain characters other than A, B, or C. If you don't want a hex FF or 00 in the work and output records, use a force-all line.



### Columns 20-22 (Overflow Field Length Entry)

These columns are used only by a summary tag along sort to eliminate the possibility of an overflow condition.

You can eliminate the possibility of an overflow condition by increasing the length of the summary data field to allow for any anticipated overflow. This can be done by coding an overflow field length entry in columns 20-22 of the field description specifications. The overflow field length entry should reflect the sum of the summary data field length and the anticipated overflow length. The entry must be right-justified to column 22, and cannot exceed the maximum field length.


Columns 20-22 are ignored for an FSZ and FSV since these fields can be only one byte long.

For example, if you want to summarize an unpacked field in positions 6-10 of your input record and you know that the output will exceed the 5-position summary field by 2 positions, specify a 7 in column 22:

0 7 F S U 6 1 0 7 7
---------------------

If packed fields are summarized, columns 20-22 should specify the number of bytes of packed data.

For example, if you want to summarize a packed field in positions 1-3 of your input record and you know that the output will exceed the 3-position packed summary field (5 numbers plus sign) by 1 position, specify a 4 in column 22 (7 numbers plus sign):



*Note:* When some include sets do not contain summary specifications, care should be taken to align the data for summarization.

### Columns 23-39

These columns are not used. Leave them blank.

#### Columns 40-72 (Comments)

Columns 40-72 are for your comments. If you instructed disk sort to print sequence specifications (column 27 of the header line is either blank or contains a zero), comments are printed along with your sequence specifications. The comments have no effect on the program's operation.

Columns 40-45 are enclosed in dotted lines on the coding sheet, because many programmers like to use these columns to write the names of fields they described in the field lines.

1

# Chapter 6. Sample Disk Sort Jobs

Each job in this section has:

1. An introduction explaining its purpose

- 2. Filled-out sequence specification sheets
- **3.** Discussion of the sequence specifications

The first six jobs use one or more of the following files and input records. (Sample Job 7 uses other files and input records, which are explained in the introduction to that job. Sample Job 8 uses the inventory file and input records, and is included to illustrate multivolume multiple device input. Sample Job 9 uses the inventory file and input records, and is included to illustrate record selection on hexadecimal input.)

Files	Records in Files	Contents of Records
Inventory file	Inventory records	Quantities of items in stock Number of transactions for each stock item
	Issue records	Shipments of items to customers
Transaction file	Receipt records	Purchases of more items from suppliers (vendors)
	Adjustment records	Corrections to inventory quantities

The format of the four types of records are shown in the following charts:

# **Record Formats for the Transaction File**

tollowing cr			Record Positions	Field Names	Contents <sup>1</sup>
Record For	mats for the Inv	ventory File			Issue Record
Inventory			1	ID	l (identifies this record as an Issue record)
Record Positions	Field Names	Contents <sup>1</sup>	2-7	ITEM	Number of the stock item to which record applies
1-6	ITEM	<i>Item information</i> Number of stock item to	8-12	QTY	Number of units ordered (5 dozen, 32 pounds, etc)
1-0		which the record applies	13-19	CUST	Customer number
7-10	CLASS	Class of the item (men's cloth-	20-27	INV	Invoice number
7-10	CLA35	ing, jewelry, etc)	28-33	DATE	Date of the order
11-24	DESC	Description of the item	34	DIS	Discount information
11-2-4	DLGC		34 35-39	PRICE	Price of the item per unit
		Stock status and reorder	40-42	CON1	The constant 001
		information	40-42	COST	Total cost of items ordered
25-27	LOC	Location of the warehouse where item is stored	43-30	0031	Receipt Record
28-29	UNIT	Unit of measure for ordering the item (by the pound, by	1	ID	R (identifies this record as a receipt record)
		the dozen, etc)	2-5	CLASS	Class of the item ordered
30-34	COST	Cost of the item per unit	2-5	ULAUU	(men's clothing, jewelry, etc)
35-39	PRICE	Price (per unit) at which	6-11	ITEM	Number of the item ordered
		item is sold	12-16	PRICE	Price of the item per unit (by
40-45	REORD	Reorder point (lowest stock quantity allowed)			the dozen, by the pound, etc)
46-50	ΩΤΥ	Number of units to order	17-22	PORDER	Purchase order number
		when reordering	23-27	QTY	Number of units ordered
51-56	BAL	Number of units in stock			Adjustment Record
58-62	ORDER	Number of units ordered, but not yet received	1	ID	A (identifies this record as an adjustment record)
69-74	AVAIL	Number of units available (BAL + ORDER)	2-7	ITEM	Number of the stock item to which record applies)
75-80	PORDER	Purchase order number	8	CODE	Adjustment code (identifies
81-86	PDATE	Date of purchase order	•	0002	reason for the adjustment)
87-91	VEND1	First vendor	9-13	ΟΤΥ	Number of units (dozen,
92-96	VEND2	Second vendor	510	arr.	pounds, etc) being added or
		Transaction activity			subtracted
97-99	TRANS	Number of transactions for this period	14-17	ОК	Authorization for the adjustment
100-105	TDATE	Data of last transaction	18-23	DATE	Date of the adjustment
106-111	ISSUES	Number of units issued dur-			
		ing this period	1	-	

<sup>1</sup> Any unsigned numeric field (packed or unpacked) can be treated as character information.

<sup>1</sup>Any unsigned numeric field (packed or unpacked) can be treated as character information.


# SAMPLE JOB 1: INCLUDE ON FIELD RELATIONSHIP

To illustrate an INCLUDE on field relationship, this sample job produces a file of inventory information for reordering stock items.


The program selects inventory records for stock items for which the quantity on hand (AVAIL field) is less than or equal to the reorder point (REORD field).

Output records are to contain information needed to reorder the items. The information is in these fields: CLASS, ITEM, DESC, UNIT, COST, QTY, AVAIL, PDATE, VEND1, VEND2, and PORDER.

Output records are to be in ascending order by class (CLASS field) and by item numbers (ITEM field) within each class.



Since there is not enough space on the first coding sheet for the last three fields, they are coded on a second sheet. To show the proper sequence for the last three fields, put a 02 in columns 1-2 of the second coding sheet:



### **Header Specifications**

### Column 6

The H identifies the line as a header line.

### Columns 7-12

SORTR identifies the job as a tag along sort.

### Columns 13-17

The control fields used to sort records in this job are CLASS and ITEM. The total of their lengths is 10, which is the entry for columns 13-17.

### Column 18

The A stands for ascending order. Output records are to be sorted into ascending order by CLASS and ITEM fields.

# Columns 29-32

The output records contain eleven fields, including two control fields (CLASS and ITEM) and nine data fields. Control fields are not being dropped (column 28 blank). Therefore, the length of the output record is the total length (64) of all eleven fields described in field specifications.

# **Record Type Specifications**

### Column 6

The I identifies the line as an include line. The input records described by the line are used by the program. All others are omitted.

### Column 8

Both factor 1 and factor 2 fields are numeric positive fields. The D in column 8 causes zeros and blanks to be considered equal in case leading zeros were not recorded.

#### Columns 9-16, 17-18, and 20-27

Inventory records for which the number of units available (AVAIL) is equal to or less than the reorder point (RE-ORD) are selected:

- Columns 9-16 identify the location of the AVAIL field (record positions 69-74).
- Columns 20-27 identify the location of the REORD field (record positions 40-45).
- Columns 17-18 define the relation between the two fields.

### Column 19

An F in column 19 indicates that factor 1 is compared to the field located by the entries in columns 20-27.

# **Field Specifications**

# Column 6

The F identifies the lines as field specification lines.

# Column 7

The first two fields described (CLASS and ITEM) are normal control fields. The rest are data fields. All are included in the output record (column 28 of header line is blank).

The records are sorted into ascending order by the CLASS field. Within each class, the item numbers (ITEM field) are in ascending order.

# Column 8

Zone and digit portions of all fields are used as they appear in the input records.

### Columns 9-16

Columns 9-16 identify the locations of fields in the input records.

CLASS Sequence	ITEM Sequence	A Sequence of Records in Sorted Output File	
Lowest class number	Lowest item number Next higher item number Third higher item number	Lowest class number — Lowest item number Lowest class number — Next higher item number Lowest class number — Third higher item number	
	Highest item number	Lowest class number — Highest item number	
Each higher class number	Lowest item number Next higher item number Third higher item number Highest item number	Class number – Lowest item number Class number – Next higher item number Class number – Third higher item number Class number – Highest item number	
Lowest item number Next higher item number Highest class number Third higher item number		Highest class number — Lowest item number Highest class number — Next higher item number Highest class number — Third higher item number	
	Highest item number	Highest class number – Highest item number	

### SAMPLE JOB 2: ADDROUT SORT

To illustrate an addrout sort, this sample job produces a record address file for an entire inventory file.

Assume that the inventory file is an indexed file. The ITEM field is the record key used in the index (the record keys are in ascending order).

This job creates a record address file containing relative record numbers of all records in the file. It sorts them into ascending order by the CLASS field. Within each class, addresses are also sorted into ascending order by ITEM field.

As a result of this job, inventory records can be processed consecutively in either of two ways:

- 1. By using the file index, which is in ascending order by ITEM field.
- 2. By using the record address file created by the disk sort program, which is in ascending order by CLASS and also by ITEM within each class.

#### **Header Specifications**

Column 6

The H identifies the line as a header line.

### Columns 7-12


SORTA identifies the job as an addrout sort.

Columns 13-17

The control fields used to sort addresses in this job are CLASS and ITEM. The total of their length is 10, which is the entry for columns 13-17.

# Column 18

The A stands for ascending order. The records are sorted into ascending order by item class (CLASS field), and by item number (ITEM field) within each class.



58

# **Record Type Specifications**

Because all input records are being used and all have the same field specifications, no record type specifications are needed (include-all is implied).

# **Field Specifications**

# Column 6

The F identifies the lines as field specification lines.

### Column 7

Both fields (CLASS and ITEM) are normal control fields. The record addresses are sorted into ascending order by CLASS field and by ITEM field within each class:

### Column 8

The C means that both zone and digit portions of the characters in the CLASS field are used in the sorting process.

The D means that only the digit portions of the characters in the ITEM field are used in the sorting process. This causes blanks to be treated as zeros.

### Columns 9-16

The CLASS field is located in positions 7-10 of the input records.

The ITEM field is located in positions 1-6 of the input records.


CLASS Sequence	ITEM Sequence	Sequence of Records in Sorted Output File	
Lowest item number Next higher item number Third higher item number Highest item number		Lowest class number — Lowest item number Lowest class number — Next higher item number Lowest class number — Third higher item number Lowest class number — Highest item number	
Each higher class number	Lowest item number Next higher item number Third higher item number Highest item number	Class number – Lowest item number Class number – Next higher item number Class number – Third higher item number Class number – Highest item number	
Highest class number	Lowest item number Next higher item number Third higher item number Highest item number	Highest class number — Lowest item number Highest class number — Next higher item number Highest class number Third higher item number Highest class number — Highest item number	

# SAMPLE JOB 3: AND LOGIC-OPPOSITE CONTROL FIELDS

The program selects inventory records for stock items in classes 0126-0130.

Output records are to contain only inventory information that indicates the activity (transactions) involving the stock items. The information is in these fields: ITEM, CLASS, TRANS, and ISSUES.

Output records are to be sorted in ascending order by class (CLASS field), and in descending order by number of transactions (TRANS field) within each class.



### **Header Specifications**

### Column 6

The H identifies the line as a header line.

## Columns 7-12

SORTR identifies the job as a tag along sort.

### Columns 13-17

The control fields used to sort records in this job are CLASS and TRANS. The total of their lengths is 7, which is the entry for columns 13-17.

#### Column 18

The A stands for ascending order. One control field (CLASS) is defined as a normal control field in field specifications. The other control field (TRANS) is an opposite control field. The records, therefore, are sorted into ascending order by item class (CLASS field), and into descending order by number or transactions (TRANS field) within each class.

### Column 28

The X indicates that control fields are being dropped from the output records because the TRANS field is an opposite control field. The program must convert the information from the TRANS field into a special form so that the records can be sorted properly. The program does not return the information to its original form after sorting. The information, therefore, would be meaningless.

The information from these two fields, however, is necessary in the output records. Therefore, the fields are also defined as data fields (see the explanation of column 7 of the field specifications for this example).

# Columns 29-32

Because control fields are dropped from the output records, the length of the output records is the total length of the fields defined as data fields in field specifications. The length is 19, which is the entry in columns 29-32.

### **Record Type Specifications**

#### Column 6

The I identifies the record type lines as include lines. The input records described by these lines are used by the program. All others are omitted.

#### Column 7

The A in column 7 means that line 02 is a continuation of the definition of the record described in line 01. A means AND. An input record must meet all conditions listed in lines 01 and 02 before it is included.

#### Column 8 👘

The D in column 8 of lines 01 and 02 means that the digit portions of the characters in positions 7-10 of the records (factor 1) is compared with the digit portion of the constants 0126 and 0130 (factor 2). Leading blanks in positions 7-10 would be treated like zeros. Therefore, \$126 (\$\not\$ is blank\$) and 0126 would be considered equal.

#### Columns 9-16, 17-18, and 20-39

Inventory records that indicate the activity (transactions) of stock classes 0126-0130 are to be selected:

- Columns 9-16 (factor 1) identify the location of the CLASS field (record positions 7-10). The CLASS field contains 4-digit class numbers.
- Columns 20-23 list constants (C in column 19), that in this example define the upper and lower limits of the classes being selected from the inventory file.
- Columns 17-18 define the relationship between the input record field being used to build the file (factor 1) and the constants in factor 2. All inventory classes equal to or greater than (GE) 0126 and equal to or less than (LE) 0130 are to be included in the sorted file.

### Columns 19 and Columns 20-39

The C in column 19 indicates that factor 1 is compared to a constant in columns 20-39. The constant in line 01 is 0130; the constant in line 02 is 0126.

# **Field Specifications**

# Column 6

The F in column 6 of lines 07-12 indicates that the lines are field specification lines.

# Column 7

Column 7 indicates the type of fields being described. The fields described in lines 07 and 08 (CLASS and TRANS, respectively) are control fields. CLASS is a normal control field. TRANS is an opposite control field. Output records are sorted so that CLASS fields are in the order indicated in column 18 of the header specifications (ascending order). Records having the same CLASS field.

The fields described in lines 09-12 are data fields. They are included in the output record but have no effect on the sequence of the records.

Note that the CLASS and TRANS fields are described once as control fields and once as data fields because TRANS is an opposite control field. Its contents in the control field portion of the output records are changed in the sorting process and would be meaningless for later processing. Therefore the control fields are dropped from the output records (X in column 28 of the header specifications) and CLASS and TRANS are defined as data fields so they would still appear in the output records.

The form of the output record is as follows:


	ITEM	CLASS	TRANS	ISSUES
Positions	1 6	7 🛶 10	11	14


# SAMPLE JOB 4: MULTIPLE INCLUDE SETS WITH FORCE


This sample job produces a history file of transaction information by selecting records for all transactions in the transaction file.

The entire file of input records is used in creating output records. The output records will be used to produce a history of the activity involving various stock items.

Output records are sorted by record type: RECEIPT records first, ISSUE records second, and ADJUST (adjustment) records last, Each type of record is sorted into ascending order by item number (ITEM field). The ISSUE records also have a subcontrol field – DATE OF ORDER.







## **Header Specifications**

## Column 6

The H identifies the line as a header line.

## Columns 7-12

SORTR identifies the job as a tag along sort.

## Columns 13-17

Three types of records are described, one on each sheet. The total length of the control fields for each type of record is 7, 13 and 7 characters, respectively. The largest of these totals (13) is the entry used in columns 13-17.

#### Column 18

The A stands for ascending order. It indicates the order into which output records (described in the three sets of field lines) will be sorted.

#### Columns 29-32

The total length of control fields for each type of record described is 7, 13, and 7 respectively. The total length of data fields for each type of record is 20, 26, and 16 respectively. The largest control field total (13) is added to the largest data field total (26) and the result (39) is used in columns 29-32.

#### **Record Type Specifications**

#### Column 6

Column 6 in line 01 of each of the three sheets contains an I indicating that the lines are include lines. The input records described by these lines are used by the program. All others are omitted.

# Column 8, Columns 9-16, Columns 17-18, Column 19, and Columns 20-39

Column 8 in line 01 of each of the three sheets contains a C indicating that the *entire character* in position 1 of the input records is to be compared with the constants R, I, and A respectively. Only input records with one of those characters in position 1 will be included in ths job.

In the record type lines, columns 9-39 have the following meanings:

- Columns 9-16 identify the input record position (position 1) being compared against R, I, and A.
- Columns 17-18 indicate the comparison result that determines whether an input record is used (the character in position 1 must equal R, I, or A).
- C in column 19 of each line indicates that the characters against which the input record character is compared are constants supplied in columns 20-39.
- Columns 20-39 supply the constants (R, I, and A, respectively) used in the comparison.

#### **Field Specifications**


Field specifications differ for the three types of records being described. The records, therefore, were described on separate coding sheets.

#### Column 6

The F in column 6 of lines 07-12 on sheet 01, lines 07-14 on sheet 02, and lines 07-12 on sheet 03 indicate that the lines are field lines.

#### Column 7

Column 7 indicates the types of fields being described for each of the three types of records. The records described by sheets 01 and 03 (RECEIPT and ADJUST records respectively) have two control fields. The records described by sheet 02 (ISSUE records) have three. The remaining fields described are data fields. These diagrams show the formats of the output records that will be created from each of the three types of input records. The numbers underneath the field identification blocks indicate the position that information will occupy in the output record.



The first control field in each type of output record is a forced control field. The number 1 will begin every RECEIPT output record, 2 will begin ISSUE records, and 3 will begin ADJUST records. This forces all RECEIPT output records to be first, all ISSUE records second, and all ADJUST records third.

The output records for this job must be the same length. The total number of characters in the control fields described for RECEIPT and ADJUST was less than the total for ISSUE records (the control field length for ISSUE on the header is used to assign the absolute length of the control field). Therefore, the program added binary zeros at the end of the control fields for RECEIPT and ADJUST output records. Blanks were added at the end of the data portion of RECEIPT and ADJUST output records to make the total length of the records equal to the total length of ISSUE output records.

## Columns 9-16 and Column 18

Columns 9-16 of the field lines identify the locations of the fields in the input records.

The first control field for each type of record is a forced control field. On each sheet, it is described by a force-all line. For this reason, columns 9-16 are blank in those lines. Column 18 identifies the character to be used in the forced control field: 1 in output records created from RECEIPT records, 2 in ISSUE output records, and 3 in ADJUST output records.

# SAMPLE JOB 5: SUMMARY SORT-ELIMINATING DUPLICATES


This sample job produces a list of inventory items requiring adjustments by selecting all adjustment records in the transaction file.

The output record is a control field consisting of the stock item number only.

Since the output record consists of no data field and, in particular, no summary data fields, the result of the SORTRS job will be to eliminate all duplicate adjustment stock item numbers from the file.

The output records, each consisting of a unique stock item number that had an adjustment, are to be in ascending order.

The output provides a list of all stock items that had an adjustment.



## **Header Specifications**

## Column 6

The H identifies the line as a header line.

## Columns 7-12

SORTRS identifies the job as a summary sort.

## Columns 13-17

Only one control field is used in this job: ITEM. Its length is 6, which is the entry for columns 13-17.

## Column 18

The A stands for ascending order.

## Columns 29-32

The output record consists of one control field only. The output record length is 6, the control field length.

#### **Record Type Specifications**

#### Column 6

The I identifies the record type line 01 as an include line. Input records described by this line are to be sorted. Since this is the only include set, all other records are omitted.

#### Column 7

Line 01 is the first (and only) include line of this include set consisting of lines 01 and 07. Therefore, column 7 must be blank.

#### Column 8

The C in column 8 tells disk sort to use both the zone and digit portions of the factor 1 and factor 2 fields described in line 01.

#### Columns 13-16, 17-18, 19, and 20

Only adjustment records containing an A in position 1 are to be included in the sort.

## **Field Specifications**

Column 6

The F in column 6 of line 07 indicates that this is a field specification line.

## Columns 7 and 8

The NC in columns 7 and 8 of line 07 indicates that it is a normal control field consisting of both the zone and digit portions of the characters in the input records included in the sort.

## Columns 9-16

Columns 9-16 of line 07 identify the location of the stock item number (having a length of 6) that is to be used as the control field.


# SAMPLE JOB 6: SUMMARY SORT-INSERTION OF CHARACTER DATA-FDV

This sample job produces a summary history file of issues by customer number by selecting all ISSUE records from the transaction file.

Using a summary sort (SORTRS), a file is to be formed consisting of each customer to whom any stock item was issued.

Each output record consists of a unique customer number, the total number of issues it had, and the total dollar value of all the issues.

The output records are to be in ascending order by customer number.



## **Header Specifications**

## Column 6

The H identifies the line as a header line.

## Columns 7-12

SORTRS identifies the job as a summary sort.

## Columns 13-17

The work record as well as the output record consists of a control field made up of the customer number. Its length is 7, which is the entry for columns 13-17.

## Column 8

The A indicates that the control field is to be sorted in ascending order.

#### Columns 29-32

The control field is not to be dropped when writing the output file. The length of the output record is the control field (seven characters) added to the data fields specified by lines 08-14 (16). This totals 23 and is the entry for columns 29-32.

#### **Record Type Specifications**

## Column 6

The I identifies the record type line 01 as an include line. Input records described by this line are to be sorted. Since this is the only include set, all others are omitted.

## Column 7

Line 01 is the first (and only) include line of this include set consisting of lines 01 and 07; therefore, column 7 must be blank.

#### Columns 8, 16, 17-18, 19, and 20

Only ISSUE records containing the full character I in position 1 of the input records are to be included in the sort.

#### **Field Specifications**

Column 6

The F in column 6 of lines 07-14 indicates that the lines are field lines.

### Columns 7 and 8

The NC in line 07 specifies that this is the control field to be sorted in the sequence specified in column 18 of the header line (ascending order) using both the zone and digit portions of the characters.

Lines 08, 09, 11, and 12 are data summary overflow fields which are used here as data field unconditional 1-character force fields.

Line 10 indicates that this is a summary data field. When the data in the input record (positions 40-42) is used to build a work record, only the digit portion of the characters is used. This is done since CON1 is an unsigned decimal number. Using a D in column 8 with signed number causes the absolute value of that value to be used.

Line 13 also is specified as a summary data field. However, U in column 8 indicates that this is signed unpacked decimal data. The sign is to be moved to the work record and used in subsequent summary additions.

Line 14 is specified as the summary overflow indicator byte.

#### Columns 9-16

Entries are placed in the from and to columns for lines 07, 10, and 13 to indicate the control field, digit summary data field (CON1), and the signed unpacked decimal summary field cost, respectively.

For lines 08, 09, 11, and 12, the entries are blank since these are overflow indicator specifications.

## Column 17


The X in line 14 defines the field as an overflow field.

## Column 18

This column is only used for lines 08, 09, 11, 12 and 14. The line numbers and the forced value in the data fields are:


08	🛿 (blank)
09	#
11	lø (blank)
12	\$
14	ø (blank)

The initial work record created from the ISSUE records will look like this:



Since this is a summary sort, the CON1 and COST fields will be summarized for records having identical control fields (CUST). These positions 10-12 (CON1) in the work records will be summarized to reflect the total number of issues (TNUMB) for a given customer number. Likewise, positions 15-22 (COST) will be summarized to reflect the total cost of all issues (TCOST).

The output record will look like this:



A blank in position 23 indicates that TNUMB and TCOST are valid sums. X in position 23 indicates that overflow occurred summarizing TNUMB and/or TCOST for this customer number giving invalid sums.

## SAMPLE JOB 7: NEGATIVE VALUES POSSIBLE

This sample job illustrates the possibility of ending up with negative values by sorting the summary history file by descending total dollars issued.

The input for this job is the output file created by *Sample Job 6.* Each input record has the following format:

Record Position	Field Name	Contents
1-7	CUST	Customer number
8-9		Constants: 10 and #
10-12	TNUMB	Total number of issues to customer
13-14		Constants: 10 and \$
15-22	TCOST	Total cost of all issues to customer
23	OFLOW	Overflow indicator:
		b — TNUMB and TCOST are valid sums
		X – Invalid sum; overflow occurred while summar- izing TNUMB and/or TCOST

Only records with valid TNUMB and TCOST will be used.

A record sort of the valid records is desired; that is, the format of the output record is to be identical to the input (the output of the second summary sort sample job).

The records are to be sorted by total dollars issued (TCOST) in descending order. It is possible that TCOST could be negative for some customer numbers. For this reason, a sort that considers the sign must occur.

#### **Header Specifications**

Column 6

The H identifies the line as a header line.

## Columns 7-12

The A record sort involving no summary data required a tag along sort. SORTR is the chosen entry.

## Columns 13-17

One type of record is specified to be included. The total length of the control fields for this type is 8 (the entry in column 17).

## Column 18

The D stands for descending order. The largest positive number comes first, the largest negative number (the negative number having the largest absolute value) comes last.

The absolute values of -19 and -99 are 19 and 99. -99 is more negative than -19 since its absolute value is greater than 19.

#### Column 28

The X indicates that the control field is to be dropped when forming the output file.

#### Columns 29-32

When the control field is dropped, only the data portion remains. This data portion is the entire input record; thus, 23 is entered in columns 29-32.

#### **Record Type Specifications**

#### Columns 6 and 7

Two record types are specified: One type is to be omitted (O in column 6); one is to be included. Each record type is specified by one record type line. Since these lines are the first (as well as the last) record type lines in their sets, column 7 must be blank.

#### Columns 8, 9-16, 17-18, 19, and 20-39

For statement 0101, these columns specify that if position 23 in the input record contains the full character constant X, the record is to be omitted.

Statement 02 includes all records not omitted by statement 01. For each record included, a work record is formed by the field specifications, statements 07 and 08. Note that the control field is an 8-position unpacked field (statement 07).

For a more complete discussion of numeric data see *Column 8* and *Columns 9-16* under *Record Type Specifications*.

## **Field Specifications**


## Column 6

The F in column 6 of statements 07 and 08 indicates that these are field lines.

#### Columns 7, 8, 9-16, and 18

Statement 07 indicates unpacked data in the control field from positions 15 through 22 of the input record. (This control field is dropped because an X has been coded in column 28 of the header specifications.)

Statement 08 indicates that the entire record is included as data.



#### SAMPLE JOB 8: MULTIPLE INPUT FILES

This sample job illustrates the use of multiple input files by producing a 5-year history of sales of selected classes of items from selected vendors.

The input is from the current year inventory file (multivolume file) and from the inventory files for the past four years (single-volume files on four input devices).

The record format for all files is the same as that used for the inventory files. The records are selected by CLASS number 0126 and VENDOR numbers 00023, 00108, and 01120.

Output records contain information needed to identify which vendor's line of this CLASS has sold the best (number of transactions and number of units) per year for the current year and the past four years. The information is in the following fields: ITEM, CLASS, VEND1, TRANS, TDATE, ISSUES.

Output records are to be sorted in ascending order by year (last two positions of TDATE field), then by VENDOR number (VEND1 field, and finally by ITEM number (ITEM field).

OCL required for the program is given in the following figure.

		<b>A</b> 11 - <b>F</b>		Form X21
BM	IBM System/3 Basic Assemble	er Coding Form		Printed in
PROGRAM		PUNCHING GRAPHIC		PAGE OF
PROGRAMMER	DATE	INSTRUCTIONS PUNCH		CARD ELECTRO NUMBER
STATEMENT				Identification- Sequence
Name Operation 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40	41 42 43 44 45 46 47 48 49 50 51	Remarks 52 53 54 55 56 57 58 59 60 61 62 (	63 64 65 66 67 68 69 70 71 72 73 74 75 76 77 78	79 80 81 82 83 84 85 86 87 88 89 90 91 92 93 94
/ LOAD SOBRT, FL				
/ FILE NAME-INPUTL, UNIT-'RL, F2, R2', PACK		F2F2, R2R2R2'		
/ FILE NAME-INPUTZ, UNIT-TL, REEL-DDDDDD,	LABEL - INVYR	04, RETAIN-94	99, BLKL-1110, RECI	L-111, RECEM-FB
FILE NAME-INPUTS, UNIT-TZ, REEL-CCCCCC,	LABEL-INVYR	03, RETAIN-94		L-111, RECEM-FB
/ FILE NAME-INPUTH, UNIT-T3, REEL-BBBBBB,	LABEL-INVYR	02, RETAIN-9	99, BLKL-1110, RECI	L-LLL, RECEM-FB
/ FILE NAME-INPUTS, UNIT-TH, REEL-AAAAAAA	LABEL-INVYR	OL RETAIN-94	99, BLKL-1110, REC	L-111, RECEM-FB
/ FILE NAME-WORK, UNIT-FL PACK-FLFLFL, TR	ACKS-20, RET	AIN-S		
/ FILE NAME-DUTPUT, UNIT-RU, PACK-RURURU,	TRACKS-20, R	ETAIN-T		
<del>┍╺┥┥┊┊┇┲┝╘┍┊┇┇┊┥┥╹┊┊┥┥┥┇┆╞┿┥┇╎┊┥┥</del> ╸┥╎╎┊ <del>┇</del>		┼╀┲┲┲┲┲	╶┼╊╁┼┼┼┼┼┾┾┾╋┾╅┼┼┼	

74

			·····					· · · · · · · · · · · · · · · · · · ·		G	X21-9089-3
IBM							Machines Corporation				inted in U.S.A.
					SEQUE		ECIFICATIONS			75 76 3 Program	7 78 79 80
						He	der		Page <b>VIZ</b>	Identification	
Line	Job		Card M	latch (S) by (X)	(J)	F Non-Verity Option(N) 96 Reserved 98 Null Output (N) 26 Storage Size to	P/Disk Sort Only				
	Card: MATCH, SORT, SELECT,	Largest sum (in bytes)	Stacker S	elect $\widehat{\mathbf{Z}} = c$		a S Opti	Length	·	<b>B</b>		
Number	MERCE	A COMMON DIALA		<del>નન</del> દી શુ દી ક	Output to	Verify Opti ved Output (N)			Description		
	Disk: SORTR,	Lengths for Any Record Type	SSPP	O S S S S S S S S S S S S S S S S S S S	Length -	erved rage	gth of				
					đ	Res Nul Sto	Ě E	46 47 48 49 50 51 52 53 54			0 70 71 70
-	6789101112 HSORTR	13 14 15 16 17		23 24 25 26 27 28	29 30 31 32 3	3 34 35 36 37	38 39 40 41 42 43 144 45	46 47 48 49 50 51 52 53 54	55 56 57 58 59 60 61	62 63 64 65 66 67 68	
	JOKIK	1 13			~6	Record					
r							Type				
Line	Fac		el.	Factor 2 (Field, Con		d)			Comments		
	ect (7	E			nstant		•				
	Type (I/O) Continuation ( C/Z/D/P/U Stacker Select	L	т I С	yword							
Number	C/Z/D/f	ation L		Location I			Record Name	1			
	F S D B From	I To G						i			
345				23 24 25 26 27 28	29 30 31 32 3	3 34 35 36 37	38 39 40 41 42 43 44 45	46 47 48 49 50 51 52 53 54	55 56 57 58 59 60 61	62 63 64 65 66 67 68	69 70 71 72
0 1	ID 7	10E	00012	6			INCLUD	E CLASS &	126 AND		
	IAD 87	916	orada	23			VENDOR	00073 06		NCLUDE	
	IDD 1		00012	G		++++	DI ACC			ассаре	
					┝╌┝╌┝╼┝╼┝	+ + + + + - +	CLT55	Ø126 AND ØØ108 OR	DICO T	11011000	
+++	IAD 87	the second se	$\alpha c \sigma \sigma r$	08		+ + + + + - + - + - + - + - + - + - + -	VENDOR	00108 OR	ALSO I	NCLUDE	
05	IDD 7	10e	QC012	6			CLHSS	0126 AND			
06	IAD 87	91E	QC011	20			VENDOR	01120			
						Fi	eld				
Line			orced						Comments		
T			be l						· ·		
	0/P/U/V)	cter	aract	Rese	rved						
Number	Type 17ype (N/O/F/C 10/P/U/V/ Ec./2/D/P/U/V/ P.com	hara	5 5 Overflow	/			Field				ſ
		ation 2	Length				Name				
	adA1 JAD	То	Subs	-	5 A						
345		13 14 15 16 17	Verflow Field Overflow Field Overflow Field Nation Overflow Field 18 19 20 21 22	23 24 25 26 27 28	29 30 31 32 3	3 34 35 36 37	38 39 40 41 42 43 44 45	46 47 48 49 50 51 52 53 54	55 56 57 58 59 60 61	62 63 64 65 66 67 68	69 70 71 72
07	FNC 104	105					TDATE	YEAR POSI	TIONS O	F DATE	
08	FNC 87	91					VEND1	VENDOR NU	MBER		
0 9	FND 1						ITEM	STOCK ITE		e	
10	FDC. 1	10	┝╌┠╌┠╌┼╌┼╴	╅┽╆┼┾┾	┝┾╍┝┥┟	+-+-+-	CIASE !	~	ITEM	┍╺╕╶┼╌┼╌┼╶┼╶┼	
<b>┣</b> ╼╡╼┥╾╂		99	┠╂╂┼┼╍	<del>┨╍┧╍┠╺┨╶┠╶┠┈</del>	+ + + + + + + + + + + + + + + + + + +	+ + + + + -	TOALC		TRANCA	TIANC	
			┝╋╋╪┿┥╸		┼╍┼╍┼╍┼╸	┼╌┼╌┼╼	KANS	NUMBER OF	KANSA	LTIONS	
	FDC 106		┠╂┠┊	<u>↓ ↓ ↓ ↓ ↓</u>	+ + + + +	+ + + +	I SUES	NUMBER C	F UNITS	TARACT	
	F										
1 4	F										
			•								

## **Header Specifications**

## Column 6

The H identifies the line as a header line.

## Columns 7-12

SORTR identifies the job as a tag along sort.

## Columns 13-17

The control fields used to sort records in this job are the last two positions of the TDATE field, and VEND1 and ITEM. The total of their lengths is 13, which is the entry for columns 13-17.

## Column 18

The A stands for ascending order. Output records are to be sorted in ascending order by YEAR, VENDOR number, and ITEM number.

#### Columns 29-32

The output records contain six fields, including the three control fields. Control fields are not being dropped (column 28 blank). The output length is the total length (26) of all six fields described in field specifications.

#### **Record Type Specifications**

#### Column 6

The I identifies the line as an include line. The input records that match the specifications of these lines are included. All other records are omitted.

#### Column 7

The A identifies the line as an AND statement while O identifies the line as an OR statement. The sequence of the lines is important in determining the include logic. The logic shown includes three types of input records, each type being included only if the two AND include requirements are met.

#### Column 8

The D means that the digit portions of the characters in positions 7-10 and 87-91 of the records (factor 1) is compared with the digit portion of the constants (factor 2). Leading blanks in positions 7-10 would be treated like zeros.

#### Columns 9-16, 17-18, and 20-39

Inventory records that indicate the activity of stock CLASS equal to the constant 0126 and vendor (VEND1 field) equal to the constants 00023, 00118, and 01120 are to be selected.

## Column 19 and 20-39

The C in column 19 indicates that factor 1 is compared to a constant in columns 20-39.

## **Field Specifications**

## Column 6

The F in column 6 of lines 7-12 indicates that the lines are field specification lines.

## Column 7

Indicates the type of fields being described. The fields described in lines 07, 08, and 09 (TDATE, VEND1, and ITEM) are control fields. N specifies they are normal control fields so that output records will be sorted in the order indicated in column 18 of the header specifications.

The fields described in lines 10-12 are data fields. The form of the output record is as follows:

	TDATE	VEND1	ITEM	CLASS	TRANS	ISSUES
Positions	1 ↔ 2	3↔7	8 🖚 13	14+++17	1820	2126

## Column 8

The C defines both the zone and digit portion of the input record used.

Statement 09 defines only the digit portion of the input record used.

## Columns 9-16

Identifies the location of the fields in the input record.

# SAMPLE JOB 9: RECORD SELECTION ON BINARY VALUES

Data selection on a binary value can be accomplished using the System/3 96-column card, 64-character set. Two types of include sequences can be used to accomplish binary selection.

## **Type 1 Include Sequence**

For binary values whose hexadecimal equivalents can be represented by one or two characters in the 64-character set (see Appendix C, *Collating Sequence*), use either an *include character* (I and C in columns 6 and 8 of the record type specifications) or an *include zone* (I and Z in columns 6 and 8 of the record type specifications )ANDed with an *include digit* (IAD in columns 6 through 8 of the record type specifications).

#### **Type 2 Include Sequence**

For binary values whose hexadecimal zone portions do not appear in the 64-character set, use two include specifications for the zone portion ANDed with an *include digit* for the digit portion.

*Example:* Select records that contain a value of 44 in position 2. The binary representation of this number is 0010 1100, which is a hex 2C. For the digit portion, select a character from the table in Appendix C with a digit portion of C (for example, <, \*, %, and @). Use the character in an include line, comparing its digit portion to the binary value of 1100. Since there is no character in the 64-character set whose zone portion is equivalent to 2, use two include lines to describe constants with a zone portion greater than 1 and less than or equal to 2. Describe these constants as packed, which reverses the zone and digit portions from hex F1 and F2 to hex 1F and 2F.

																																	R	ec	:0	ď	Ty	٧p	e																															
Г	Lin	e	1	5	Τ			F	acto	or 1	1			1	Rel.					F	act	or 2	2 (F	ielo	3, C	Cons	tan	t, o	r K	еуи	/or	d)						Τ														(	Com	me	nts															7
N:	umbe		i tuo	C/7/D/b/il	Stackor 0	1		om	1	tion	т	°0 15	- 16				-	 F	K	Li n	oca 	tior	 , T/	-	ן – ו ו	-Coi				32	33	3 34	. 3	5 34	5 3	7 38		4			Na	- cor me					49	50	51	52	53	54	55 1	56 5	57 5	8 5	i9 6	50 6	51	62	63	64	65 (	66 6	57 6	8 6	9 7	0 71	1 7	2
0	1	I		Z	7	Ť	T	1	1	Ţ		Γ	2	E	K	)Ł	k	2	Τ	Τ	T	Τ	٦	1		Ē		Γ	Γ	T	Τ	Т	Ţ	Т	T	Ţ	Τ	I	)1	G	I	7	1	3		Ċ	1	Γ	Γ	Γ	Γ		Τ	T	Τ	Τ	Ι	Τ	Τ	٦	T			T	Τ	Τ	Т	Т	Т	1
0	2	I	A	4 F	1	T							2	<b>T</b>	E	C	1	2	T	1	T					i l		1			T	1	T					K	IN	D	)	K		H	E	İΧ		2	F	1																1		T	T	1
٥	3	I			9	T							2	G	7	6		(	T		T		1			ī		Γ		Γ			T					6	Ŵ	D		>	-	H	'e	X	1	1	F																					
0	4			T													Τ		Τ							i							T					Γ					Γ			1																							Τ	
0	5						T															Ι				1																				1 													T							ſ				
0	6		Γ														Ι																					Γ								l																								


	Hexadecimal Value		Binary Value		Decimal Value
Field to be selected	2C	=	0010 1100	=	44
Character @	7C	=	0111 1100		124
Packed character 2	2F	=	0010 1111	H	47
Packed character 1	1F	=	0001 1111	=	31

The record type specifications shown will cause selection of all records containing (in column 2) a value between 31 (hex 1F) and 47 (hex 2F) whose digit portion is equal to C.


*Note:* The 32 hexadecimal values whose zone portions are either A or B cannot be accessed with these types of entries. Therefore, there can be no record selection based on these values.

## Sample Sort Job 9 Description

The purpose of this sample job is to select records from an inventory file whose reorder point is 7800. The reorder point is a 2-byte quantity in columns 44 and 45 of the inventory records. The quantity is stored in binary (7800 = 0001 1110 0111 1000), and the hexadecimal representation of this number is 1E78. (Use Appendix C to help with binary and hexadecimal conversions.)



	Hexadecimal Value		Binary Value		Decimal Value
Field to be selected, column 44	1E	=	0001 1110	Ξ	30
Character +	4E	=	0100 1110	=	78
Packed character 1	1F	=	0001 1111	=	31
Packed character 0	OF	=	0000 1111		15
Field to be selected, column 45	78	=	0111 1000		
Character @	7C	=	0111 1100		
Character 8	F8	. =	1111 1000		



These specifications will cause selection of all records containing (in column 44) a value between 15 (hex 0F) and 31 (hex 1F) whose digit portion is equal to E. These specifications will further limit selection of records to those which have a binary value in column 45 whose zone portion equals 7 and whose digit portion equals 8. Therefore, all records selected will have hex 1E78 in columns 44 and 45.

## **Header Specification**

Column 6

The H identifies the line as a header line.

### Columns 7-12

SORTR identifies the job as a tagalong sort.

#### Columns 13-17

The total length of the control field is 6 bytes.

#### Column 18

The A stands for ascending order. The file will be sorted according to the standard collating sequence shown in Appendix C.

#### Columns 29-32

The control field is not dropped when data is written to the output file (column 28 is blank). Therefore, the length of the output record equals the length of the control field (6 bytes) plus the length of the data field (105 characters) specified by lines 07 and 08. This output record length totals 111, which is the entry for columns 29 through 32.

#### **Record Type Specifications**

Line 01 selects records whose digit portion in column 44 is E. Lines 02 and 03 select records whose packed value in column 44 is less than or equal to hex 1F, and at the same time is greater than a packed value of hex 0F.

The only hexadecimal values that satisfy both specifications for lines 02 and 03 are hex 11 through hex 1F. Line 04 is a comment line. Lines 05 and 06 select records whose zone portion in column 45 is 7 and whose digit portion is 8.

## **Field Specifications**

Column 6


The F identifies the lines as field specification lines.

#### Columns 7, 8, and 9-16

Line 07 indicates that the control field is in positions 1 through 6 of the input records. Only the digit portions of the characters will be used. This control field will be included in the output file.

Line 08 indicates that the other 105 input record characters are included as data in the output file.

# SAMPLE JOB 1: SORTING ON A CONTROL FIELD THAT CONTAINS EITHER A POSITIVE INTEGER OR A POSITIVE REAL NUMBER



## **Header Specification**

## Column 6

The H identifies the line as a header line.

## Columns 7-12

SORTR identifies the job as a tagalong sort.

## Columns 13-17

The control field that contains either a positive integer or a positive real number has a length of 4 bytes (the entry in column 17).

## Column 18

The A specifies ascending order. The smallest positive integer or positive real number comes first; the largest positive integer or positive real number comes last in the sort sequence.

## Columns 29-32

The control field is not dropped when data is written to the output file (column 28 is blank). Therefore, the length of the output record equals the length of the control field (4 bytes) added to the length of the data field (60 characters) specified by lines 07 and 08. This output record length totals 64, which is the entry for columns 29 through 32.

## **Record Type Specifications**

Because all input records are being used and all have the same field specifications, no record type specifications are needed (include-all is implied).

#### **Field Specifications**


Column 6


The F identifies the lines as field specification lines.

## Columns 7, 8, and 9-16

Line 07 indicates that the control field is in positions 1 through 4 of the input record. This control field is included in the sorted output file (column 28 of the header line is blank).

# SAMPLE JOB 2: SORTING ON A CONTROL FIELD THAT CONTAINS ONLY A POSITIVE OR NEGATIVE INTEGER





## **Header Specification**

#### Column 6

The H identifies the line as a header line.

## Columns 7-12

SORTR identifies the job as a tagalong sort.

## Columns 13-17

The total length of the control field (for either a positive or a negative integer) is 5 bytes (the entry in column 17).

## Column 18

The A stands for ascending order. Since negative integers are stored in two's complement form, the smallest negative integer comes first; the largest positive integer comes last in the sort sequence (for example, -2, -1, 0, 1, 2).

## Column 28

The X indicates that the control field is dropped when data is written to the output file.

## Columns 29-32

When the control field is dropped, only the data portion remains. The data portion in this sample job is the entire input record. Therefore, 64 is entered in columns 29 through 32.

## **Record Type Specifications**

## Column 6

Two record types are specified (positive integers and negative integers). Both record types are to be included (I in column 6 of line 01, pages 01 and 02).

## Columns 8, 9-16, 17-18, 19, and 20-39

On line 01 (page 01), these columns specify that if position 1 (the leftmost byte of the 4-byte control field from the input record) is less than or equal to the character constant " (see note), the work record will have a character 2 forced into the first byte of its 5-byte control field (line 07 on page 01). This include line selects only positive integers. Line 01 (page 02), which is an include-all line, indicates that all records not described by the first include line (page 01) are also included in the sort. The first include line (line 01 on page 01) selects all positive integers, therefore, this include-all line (page 2) selects all negative integers, which will have a character 1 forced into the first byte of their work record control field (line 07 on page 02). All negative integers are forced in front of all positive integers in the sort sequence.

*Note:* The special character "has a bit configuration of 01111111, which is equivalent to the high order byte of the maximum positive integer.

## **Field Specifications**

#### Column 6


The F identifies the lines on pages 01 and 02 as field specification lines.


## Columns 7, 8, 9-16, and 18

On line 07 (pages 01 and 02), these columns specify that for positive integers (line 07 on page 01), a character 2 will be forced into the first byte of the work record control field; for negative integers (line 07 on page 02), a character 1 will be forced into the first byte of the work record control field.

On line 08 and 02, columns 7, 8, and 9 through 16 specify that the control field is in positions 1 through 4 of the input records. (The control field is not included in the output records because header specification column 28, page 01, contains an X.)

# SAMPLE JOB 3: SORTING ON A CONTROL FIELD THAT CONTAINS ONLY A POSITIVE OR NEGATIVE REAL NUMBER





## **Header Specification**

## Column 6

The H identifies the line as a header line.

## Columns 7-12

SORTR identifies the job as a tagalong sort.

## Columns 13-17

The total length of the control field (for either a positive or negative real number) is 5 bytes (the entry in column 17).

## Column 18

The A stands for ascending order. The smallest negative real number comes first; the largest positive real number comes last in the sort sequence (for example -2.0, -1.0, 0.0, 1.0, 2.0).

## Column 28

The X indicates that the control field is dropped when data is written to the output file.

## Columns 29-32

When the control field is dropped, only the data portion remains. The data portion in this sample job is the entire input record. Therefore, 64 is entered in columns 29 through 32.

#### **Record Type Specifications**

## Column 6

Two record types are specified (positive real numbers and negative real numbers). Both types are to be included (I in column 6 of line 01, pages 01 and 02).

## Columns 8, 9-16, 17-18, 19, and 20-39

On line 01 (page 01), these columns specify that if position 1 (the leftmost byte of the 4-byte control field from the input record) is less than or equal to the character constant " (see note), the work record will have a character 2 forced into the first byte of its 5-byte control field (line 07 on page 01). This include line selects only positive real numbers. Line 01 (page 02), which is an include-all line, indicates that all records not described by the first include line (page 01) are also included in the sort. The first include line (line 01 on page 01) selects all positive real numbers; therefore, this include-all line (page 02) selects all negative real numbers, which will have a character 1 forced into the first byte of their work record control field (line 07 on page 02). All negative real numbers are forced in front of all positive real numbers in the sort sequence.

*Note:* The special character " has a bit configuration of 01111111, which is equivalent to the high order byte of the maximum positive real number.

#### **Field Specifications**

#### Column 6

The F identifies the lines on pages 01 and 02 as field specification lines.

## Columns 7, 8, 9-16, and 18

On line 07 (pages 01 and 02), these columns specify that for positive real numbers (line 07 on page 01), a character 2 will be forced into the first byte of the work record control field; for negative real numbers (line 07 on page 02) a character 1 will be forced into the first byte of the work record control field.

On line 08 (pages 01 and 02), columns 7, 8, and 9 through 16 specify that the control field is in positions 1 through 4 of the input records. Note that real numbers are always carried in true form (never in two's complement form). Therefore, sorting negative real numbers into ascending sequence requires them (when treated as character fields) to be sorted into descending sequence.

On line 09 (pages 01 and 02), columns 7, 8, and 9 through 16 specify that 64 input record characters are included as data in the sorted output file.

The OCL cycle you use depends on the type of sort you want to do:

Type of Sort	Cycle To Use	What The Cycle Does
Sort job you plan to run only a few times	LOAD	Gives the system the OCL statements it needs to run the sort job.
	BUILD	Stores the OCL statements necessary to run the sort job in a source library. <sup>1</sup>
Sort job you plan to run frequently	CALL	Tells the system you want to use a procedure <sup>1</sup> to run a sort job.
	BUILD	Stores the OCL statements necessary to run the sort job in a source library. <sup>1</sup>
Sort job you plan to run as one of a group of jobs	BUILDC	Puts the name of each job in the group and the disk location of the OCL state- ments for each job in a source library. <sup>1</sup>
	CALL	Tells the system you want to use the BUILDC proce- dure <sup>1</sup> to run a group of jobs.
<sup>1</sup> A set of OCL state	ements in a source l	ibrary is called a procedure.

*Note:* See Appendix H for CCP/Disk Sort oriented file and program considerations.

## CODING OCL CYCLES

This appendix contains keyword-response summary charts for the LOAD, BUILD, and CALL cycles. For the keywordresponse summary for the BUILDC cycle, see the *IBM System/3 Model 6 Operation Control Language and Disk Utility Programs Reference Manual*, GC21-7516.

- Words or letters in all capital letters (such as INPUT, INCLUDE, R1) are entries the operator must make.
- Words or letters not in all capital letters (such as procedure name, mmddyy) represent information you must supply.
- P/S indicates the program start (PROG START) key.
- ENTER- indicates the ENTER key.

For more information about any particular statement (keyword and response), see the keyword description section of the *IBM System/3 Model 6 Operation Control Language and Disk Utility Programs Reference Manual*, GC21-7516.

## THE MODIFY STATEMENT

The only responses shown on the following charts are those that apply directly to the disk sort program. For other MODIFY options (such as correcting one of the statements in a cycle) see the keyword description section of the *IBM System/3 Model 6 Operation Control Language and Disk Utility Programs Reference Manual*, GC21-7516.

# THE LOAD CYCLE

Prompt	Response	Considerations
READY	LOAD (P/S)	
LOAD NAME	\$DSORT (P/S)	System name for the disk sort program
UNIT	R1, R2, F1, or F2 (P/S)	Disk that the disk sort program is on
DATE	mmddyy or ddmmyy (P/S)	If you want a different system date for your job
	or	
	(P/S)	If you want to use the system date for your job or no date is required
SWITCH	(P/S)	Disk sort does not use external indicators
FILE NAME	INPUT (P/S)	Name that disk sort uses for file you want to sort
UNIT	R1, R2, F1, or F2 (P/S)	Which disk the file you want to sort is on
РАСК	Disk name (P/S)	Name of disk which contains the file to be sorted
LABEL	VTOC filename (ENTER-)	Name you use for the file you want to sort (PAYROLL, INVENT, etc.)
FILE NAME	WORK (optional) (P/S)	Name disk sort uses to refer to file you are going to use for work area during this sort. If WORK is not used, disk sort performs automatic work file allocation.
UNIT	R1, R2, F1, or F2 (P/S)	Disk containing the file you are going to use for a work area
РАСК	Disk name (P/S)	Name of disk which contains the work file
LABEL	(P/S)	_

Input file

# THE LOAD CYCLE (continued)

Work file

Output file

Prompt	Response	Considerations
RECORDS	(P/S)	Do not specify RECORDS for the work file
TRACKS	1-398 (P/S)	Number of tracks file occupies (see Appendix E)
LOCATION	8-405 (P/S)	If you want to control the location of the file on the disk
	or	
	(P/S)	If you want to let disk sort control the location of the file on the disk
RETAIN	S (ENTER-)	Scratch status because the work file is used for only one sort job
FILE NAME	OUTPUT (P/S)	Name disk sort uses for the sorted file
UNIT	R1, R2, F1, or F2 (P/S)	The disk you want to put the sorted file on
РАСК	Disk name (P/S)	Name of the disk which will contain the sorted file
LABEL	VTOC filename (P/S)	Name you use for the sorted file (this can be the same as your name for the file you want to sort)
RECORDS (see note)	1-999999 (P/S)	Number of records you want to sort
TRACKS (see note)	1-398 (P/S)	Number of tracks file occupies (see Appendix E)
LOCATION	8-405 (P/S) or	If you want to control the location of the file on the disk (if you are overlay- ing an input file with an output file you must specify LOCATION)
	(P/S)	If you want to let disk sort control the location of the file on the disk
RETAIN	P or T (P/S)	If the output file is built during the sort job, it can have permanent (P) or tempor- ary (T) status. If the output file existed before you started the sort job, the file cannot have permanent status since you cannot overlay a permanent file.

 Note:
 These are the space keywords. If you are creating a new output file you must respond

 to one of them.
 Integer (Binary) and Real Number Sorting
 93

# THE LOAD CYCLE (continued)

	Prompt	Response	Considerations
	FILE NAME	(P/S)	Disk sort uses only three files
	MODIFY	RUN (P/S)	Tells disk sort that the OCL statements are complete
If you are going to enter sequence specifications from the key- board		<ol> <li>Sequence specifications</li> <li>// END</li> </ol>	<ol> <li>Operator is going to enter the sequence specifications from the keyboard (one specification per line)</li> <li>Sequence specifications are com- plete</li> <li>Disk sort program sorts your file</li> </ol>
		// SOURCE name, unit	<ol> <li>name = name of the KSE-created source library entry which contains the set of sequence specifications you want to use.</li> </ol>
If the sequence specifications are in a KSE-created source library entry			unit = the disk (R1, R2, F1, or F2) whose source library contains the sequence specifications you want to use.
			2. When all these sequence specifica- tions have been read, the disk sort program sorts your file

## THE BUILD CYCLE

Prompt Response		Considerations	
READY	BUILD (P/S)		
BUILD NAME	Procedure name (P/S)	<ul> <li>The name you want to give the procedure:</li> <li>Maximum of six alphameric characters</li> <li>Must begin with alphabetic character</li> <li>Must not be DIR, SYSTEM, or ALL</li> </ul>	
UNIT	R1, R2, F1, or F2 (P/S)	The disk containing the source library you want to put the procedure in	
LOAD NAME	\$DSORT (P/S)	System name for the disk sort program	
UNIT	R1, R2, F1, or F2 (P/S)	Disk that the disk sort program is on	
DATE	ddmmyy or mmddyy (P/S)	If you want a different system date for your job	
	or		
	(P/S)	If you want to use the system date for your job or no date is required	
SWITCH	(P/S)	Disk sort does not use external indicators	
FILE NAME	INPUT (P/S)	Name that disk sort uses for file you want to sort	
UNIT	R1, R2, F1, or F2 (P/S)	Disk the file you want to sort is on	
РАСК	Disk name (P/S)	Name of disk that contains the file to be sorted	
LABEL	VTOC filename (ENTER-)	Name you use for file you want to sort (PAYROLL, INVENT, etc.)	

Input file

# THE BUILD CYCLE (continued)

Prompt	Response	Considerations Name disk sort uses to refer to file you are going to use for work area during this sort. If WORK is not used, disk sort performs automatic work file	
FILE NAME	WORK (optional) (P/S)		
<u></u>		allocation.	
UNIT	R1, R2, F1, or F2 (P/S)	Which disk the file you are going to us for work area is on	
РАСК	Disk name (P/S)	Name of disk that work file is on	
LABEL	(P/S)		
RECORDS (P/S)			
TRACKS 1-398 (P/S)		Number of tracks file occupies (see Appendix E)	
LOCATION	8-405 (P/S)	If you want to control the location of the file on the disk	
	or		
	(P/S)	If you want to let disk sort control the location of the file on the disk	
RETAIN S (ENTER-)		Scratch status because the work file is used for only one sort job	

Work file

# THE BUILD CYCLE (continued)

Output file

Prompt	Response	Considerations	
FILE NAME	OUTPUT (P/S)	Name that disk sort uses for file area where you want to put the sorted file	
UNIT	R1, R2, F1, or F2	Disk you want to put the sorted file on	
РАСК	Disk name (P/S)	Name of disk which will contain the sorted file	
LABEL	VTOC filename (P/S)	Name you use for the sorted file (this can be the same as your name for the file you want to sort)	
RECORDS (see note)	1-999999 (P/S)	Number of records you want to sort	
TRACKS (see note)	1-398 (P/S)	Number of tracks file occupies (see Appendix E)	
LOCATION	8-405 (P/S)	If you want to control the location of the file on the disk	
	Or		
	(P/S)	If you want to let disk sort control the location of the file on the disk	
RETAIN P or T (ENTER-)		If the output file is built during the sort job, it can have permanent (P) or tempor ary (T) status. If the output file existed before you started the sorted job, the file cannot have permanent status since you cannot overlay a permanent file	

*Note:* These are the space keywords. If you are creating a new output file you must respond to one of them.

# THE BUILD CYCLE (continued)

You are going to include sequence specifications in the procedure

Prompt	Response	Considerations
FILE NAME	(P/S)	Disk sort uses only three files
MODIFY	<ol> <li>INCLUDE</li> <li>Sequence specifications</li> <li>// END</li> </ol>	<ol> <li>Tells the system you are going to include sequence specifications in the procedure</li> <li>Operator types the specifications (one specification per line)</li> <li>Tells the system the sequence specifications are complete</li> </ol>
MODIFY	RUN (P/S)	System gives operator opportunity to correct any mistakes in sequence specifications. Operator types RUN when su all the specifications are correct. Syste stores the procedure in the source libra you specified in the second OCL state- ment.
MODIFY	<ol> <li>INCLUDE</li> <li>// SOURCE name, unit</li> </ol>	<ol> <li>Tells the system you are going to include in the procedure a pointe to the sequence specifications</li> <li>name = name of the KSE-created source library entry which contai the set of sequence specifications you want to include in the proce dure unit = the disk (R1, R2, F1, or F whose source library contains the set of sequence specifications you want to include in the procedure</li> </ol>
MODIFY	RUN (P/S)	You are not going to include sequence specifications in the procedure. The system stores the procedure in the source library you specified in the second OCL statement.

You are not putting sequence specifications in


the procedure

You are going to put a pointer to the sequence specifications in the procedure

# THE CALL CYCLE

-	Prompt	Response	Considerations
	READY	CALL (P/S)	
	CALL NAME	Procedure name (P/S)	Your response to BUILD NAME during the BUILD sequence
	UNIT	R1, R2, F1, or F2 (P/S)	Disk where the procedure is located; sys- tem displays the procedure
an an an an ann an Aonaichtean An Aonaichtean an Aonaichtean An Aonaichtean An Aonaichtean	MODIFY	RUN (P/S)	Tells the system the OCL statements are correct
equence	INCLUDED STATEMENTS	No response	System prints sequence specifications
cifications included in procedure	MODIFY	RUN (P/S)	Tells the system the sequence specifica- tions are correct; system runs the sort job
equence cifications are in the proce- e and you want enter them bugh the board	MESSAGE SD100 ASKING FOR SEQUENCE SPECIFICATIONS	<ol> <li>Sequence specifications</li> <li>// END</li> </ol>	<ol> <li>Operator types sequence specifica- tions on the keyboard (one specifi cation per line)</li> <li>Tells the system the sequence specifications have been entered</li> </ol>
equence cifications are in the procedure are in a KSE- ated source ary entry	MESSAGE SD100 ASKING FOR SEQUENCE SPECIFICATIONS	// SOURCE name, unit	name = name of the KSE-created source library entry which contains the sequence specifications you want to use. unit = location of disk whose source library entry you want to use (R1, R2, F1, or F2) When the system has read all the sequence


# Appendix B. Supplying Sequence Specifications



### INTERRELATIONSHIP OF CONVERSATIONAL OCL AND SEQUENCE SPECIFICATIONS (MODEL 6)

The following chart shows the skeleton of the OCL LOAD and CALL cycles: the first two keywords and any other keywords that are of special significance in the interrelationship of the OCL and the sequence specifications. The rest of the keywords (indicated by arrows) follow the normal sequence for that cycle. (Appendix A contains the keyword-response summaries for each of the three cycles.)

The gray areas in each box show where the sequence specifications fit into the OCL cycle.





#### **Supplying Sequence Specifications**


Operator will type sequence specifications on the keyboard (one statement per line).

Sequence specifications are in a KSE-created source library entry. To use the specifications, enter a SOURCE statement to give the system the name of the KSE entry and its disk location.

Sequence specifications have been included in a procedure—along with the OCL statements for the job. To use the specifications, enter CALL NAME and UNIT statements to give the system the name of the procedure and its disk location.







### WHICH OCL AND SEQUENCE SPECIFICATION METHOD TO USE FOR THE MODEL 10, THE MODEL 12, AND THE MODEL 15

The method you use to supply OCL and sequence specifications depends on the type of sort you want to do:

Type of Sort	Method to Use	How the Method Works
Sort jobs you plan to run only a few times	OCL from system input device; sequence specifi- cations from system input device	You supply both OCL and sequence specifications through the system input device.
Sort jobs you plan to run repetitively	Both OCL and sequence specifications from pro- cedure section of source library (maximum of 25 specification statements allowed in procedure)	You place the OCL statements and sequence specifications (see note) in the procedure section of the source library using library maintenance, then access them with CALL and RUN statements.
Sort jobs you plan to run using the same file but dif- ferent sequence specifications	OCL from procedure section of source library; sequence specifications from system input device	You place OCL statements in the pro- cedure section of the source library, then access them using CALL and RUN statements. You supply sequence specifications through the system input device.
	OCL from system input device; sequence specifi- cations accessed from source section of source library by SOURCE statement from the system input device	You supply OCL from the system input device. The SOURCE statement accesses sequence specifications (see note) which you have placed in the source sec- tion of the source library.
	OCL from the procedure section of source library; sequence specifications accessed from source sec- tion of source library by SOURCE statement from the system input device or from the pro- cedure section of the source library	You place OCL statements in the pro- cedure section of the source library, then access them using CALL and RUN statements. The SOURCE statement accesses sequence specifications (see note) which you have placed in the source section of the source library.

*Note:* When being copied to the source library, the sequence specifications must be followed by a END statement.

## Appendix C. Collating Sequence

						1			
When Both Characters	a Zone and Digi are Used	it Portions of	When Only Characters	the Zone Port is Used	ion of	When Only Characters	y the Digit Porti s is Used	ion of	
Order in the Sequence <sup>1</sup>	Character	Corresponding Hexadecimal Number <sup>2</sup>	Order in the Sequence <sup>1</sup>	Character	Corresponding Hexadecimal Number <sup>2</sup>	Order in the Sequence <sup>1</sup>	Character	Corresponding Hexadecimal Number <sup>2</sup>	
1 (lowest)	blank	40		¢	4A 4B		blank E	40 50	
2	¢	<u>4A</u>	1	< .	4C	1 .1	– (minus)	60	
3 4	<	4 <u>B</u> 4C	(lowest)	+	4D 4E	(lowest)		DO	
5	$\overline{i}$	40 4D	$(a_1, a_2, \dots, a_n) \in \mathbb{R}^n$		4E 4F	-	0	FO	
6	+	4E		1	5A		<u> </u>	61	
7		4F		\$	5B	2	А	C1	
8	<u>د</u>	50	2		5C	1 -	J	D1	
10	\$	5A 5B		) • •	5D 5E		1 B	F1 C2	
11	*	5C			5F		ĸ	D2	
12	)	5D			61	3	S	E2	
13	<u></u>	5E	1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 - 1997 -		6B		2	F2	
14	<b>7</b>	5F		%	6C		С	C3	
15 16	- (minus)	<u>60</u> 61	3	(underscore)	6C	4		D3 E3	
17		6B		(underscore)	6E		3	F3	
18	%	6C		2	6F		D	C4	
19		6D		:	7A	5	М	D4	
	(underscore)			#	7B		U	E4	
20 21	>	6E 6F	4	@	7C - 7D		4 E	F4 C5	
22	:	7A	4	(apostrophe)	10	1	E N	D5	
23	#	7B		=	7E	6	v	E5	
24	0	7C		· //	7F		5	F5	
25		70		Ę	50		F	C6	
26	(apostrophe)	75		A B	C1	7	O W	D6	
20		7 <u>E</u> 7F		C	C2 C3	1	6	E6 F6	
28	A	C1		5 D E F	C3	<u></u>	G	C7	
29	В	C2	5		C5		P	D7	
30	С	C3			<sup>.</sup> C6	8	X	E7 _	
31	<u>D</u>	<u>C4</u>		G	C7		7	<u>F7</u>	
<u>32</u> 33	E F	C5 C6	H H	H	C8 C9		H · · · ·	C8 D8	
34	G	C8 C7		- (minus)	60	9	Y	E8	
35	H	C8		)	DO		8	F8	
36	1	C9		Ş			Ī	C9	
37	· }	D0		J	D1 ·	10	R	D9	
38	<u> </u>	D1		ĸ	D2		Z 9	E9 F9	
39	 К	D1 D2	6	M		D3 D4			4A
40	<u>N</u>	D3			D5	11	¢	5A	
41	М	D4	· · ·	0	D6			7A	
42	N	D5		Р	D7			4B	
43 44	0	D6		Q	D8	12	\$	5B	
44 45	P Q	D7 D8		R S	<u>D9</u> E2	1	,	6B	
46	R	D8 D9		т Т	E2		#	7B 4C	
47	S	E2		U	E4		* .	5C	
48	T	E3	7	V	E5	13	%,	6C	
49	<u> </u>	E4	1.0	W	E6		@	7C	
50 51	W	E5 F6		X Y	E7 E8		(	4D	
51	X	E6 E7		Υ Ζ	E8 E9		)	5D 6D	
53	Y	E8		blank	40	14	(underscore)		
54	Z	E9		0	F0		,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	7D	
55	0	FO		1	F1		(apostrophe)		
56 57	1 2	F1 F2		2	F2		+	4E	
58	3	F2 F3	8	3 4	F3 F4	15		5E	
59	4	F4	(highest)	5	F5		;; > =	6E 7E	
60	5	F5		6	F6			7E 4F	
61	6	<u>F6</u>		7	F7	16	i i l	5F	
62 63	7	F7		8	F8	(highest)		6F	
64	8 9	F8 F9		9	F9		"	7F	
highest)	Ŭ.	10							

<sup>&</sup>lt;sup>1</sup>When several characters share the same position in the sequence, they are considered equal. For example, if you are using only the digit portion of characters; H, Q, Y and 8 (position 9) are considered equal. <sup>2</sup>This is the number you use in ALTSEQ statements to identify a character you want to shift to a different order in the sequence.

### STANDARD COLLATING SEQUENCE

The standard collating sequence chart shows the three standard collating sequences for System/3:

- Standard collating sequence when both zone and digit portions of characters are being used
- Standard collating sequence when only the zone portion of characters is being used
- Standard collating sequence when only the digit portion of characters is being used

### ALTERNATE COLLATING SEQUENCE

If you want to change the standard collating sequence, you must code an S in column 26 of the header specification and code ALTSEQ statements. You can code as many ALTSEQ statements as you need. Each one must begin with ALTSEQ and can contain a maximum of 96 positions.


Note: Do not use a packed or unpacked factor 1 in an include or omit record type specification (P or U in column 8) if you specify an alternate collating sequence.

### **Coding Rules**


1. Code ALTSEQ in the first six positions to tell disk sort you want to alter the standard collating sequence:



2. Leave the next two positions blank:



3. Enter the hex equivalent<sup>1</sup> of the character you are taking out of its normal sequence:



4. Enter the hex equivalent<sup>1</sup> of the value the character specified in columns 9 and 10 is to assume in the collating sequence:

A L T S E Q h h h n (hn = hex number)

- 5. Enter as many pairs of 3 and 4 as the number of characters you are taking out of normal sequence.
- 6. Leave no spaces between sets of hex numbers:

- When you reach the end of one statement, you can continue on the next specification line (follow rules 1-6).
- 8. Enter a double asterisk in positions 1 and 2 to indicate the end of the ALTSEQ statements:

	Α	L	Т	s	Е	٥		h	n	h	n		+	maximum of 96 positions
	Α	L	Т	S	Е	٥		h	n	h	n	_	+	maximum of 96 positions
	Α	L	т	S	E	Q		h	n	h	n	_	+	maximum of 96 positions
$\langle$	*	*	$\supset$											

<sup>1</sup>See standard collating chart for hex equivalents of all System/3 characters.

#### Input Order When ALTSEQ Statements Are Used

ALTSEQ statements follow the header line. When you use an alternate collating sequence, your input must be in this order:

- 1. OCL statements
- 2. Sequence specifications
  - a. Header line
  - b. ALTSEQ statements
  - c. \*\*
  - d. Record type and field description lines as required
- 3. File to be sorted

#### **Programming Considerations**

When you move a character into the sequence position normally assigned to another, both the new and the original character occupy the same position and are considered equal (see the first sample ALTSEQ statement). If you do not want the two characters to be equal, you must also move the character that normally occupies that position (see the second ALTSEQ statement).

#### Programming Considerations With Card or 3741 Input

Whenever a record is padded on the right with blanks, the padded area is altered by the ALTSEQ logic.

#### Effect of ALTSEQ Statements on Other Coding

ALTSEQ statements can change:

- Factor 1 and factor 2
- Normal and opposite control fields
- Control field characters before they are replaced or added to by forced fields

ALTSEQ statements never change data fields in records or forced control field characters.

#### Sample ALTSEQ Statements

To change the sequence of one character:

ALTSEQ	ALTSEQ	40F0
Statements	* *	

Explanation Blank (40) is moved to the position in the collating sequence occupied by zero (F0). Blanks are zeros, therefore, are considered equal.

To change the sequence of several characters:

ALTSEQ Statements

ALTSEQ 5BC8C8C9C9D1 s \*\*

Explanation 5BC8 moves \$ (5B) to the position occupied by H (C8).
C8C9 moves H (C8) to the position occupied by I (C9).
C9D1 moves I (C9) to the position occupied by J (D1).
The \$, therefore, has been inserted between G and H, as follows:
A,B,C,D,E,F,G,\$,H,I, (I and J occupy the same position).

#### **PROGRAMMING AIDS**

A *Translation Table and Alternate Collating Sequence Coding Sheet,* X21-9096, is available for you to use to keep track of changes you make to the collating sequence.

IBM

#### International Business Machines Corporation

Form X21-9096 Printed in U.S.A.

#### TRANSLATION TABLE AND ALTERNATE COLLATING SEQUENCE CODING SHEET

	System/3		Replaced By/Takes		System/3		Replaced By/Takes		System/3		Replaced By/Takes		System/3	_	Replaced By/Takes		System/3		Replace By/Tak
Code	Graphic	Entry	Place Of	Code	Graphic	Entry	Place Of	Code	Graphic	Entry	Place Of	Code	Graphic	Entry	Place Of	Code	Graphic	Entry	Place O
0000000		00		00110011		33		01100110		66		10011001		99		11001100		CC	L
00000001		01		00110100		34		01100111		67		10011010		9A		11001101		CD	
0000010		02		00110101		35		01101000		68		10011011		9B		11001110		CE	
00000011		03		00110110		36		01101001		69		10011100	· · · · ·	9C		_11001111		_CF	
00000100		04		00110111		37		01101010		6A		10011101		9D		11010000	}	DO	
0000101		05		00111000		38		01101011		6B		10011110		9E		11010001	J	D1	
0000110		06		00111001		39		01101100	%	6C		10011111		9F		11010010	к	D2	
0000111		07		00111010		3A		01101101	-	6D		10100000		A0		11010011	L	D3	
0001000		08		00111011		3B		01101110	>	6E		10100001		A1		11010100	M	D4	
0001001		09		00111100		3C		01101111	?	6F		10100010		A2		11010101	N	D5	
0001010		0A		00111101		3D		01110000		70		10100011		A3		11010110	0	D6	
0001011		OB	· · · · · · · · · · · · · · · · · · ·	00111110	1	3E		01110001		71		10100100		A4		11010111	Р	D7	
0001100		OC		00111111		3F		01110010		72		10100101		A5		11011000	Q	D8	
0001101		0D		01000000	Blank	40		01110011	l	73		10100110		A6	<b>↓</b>	11011001	R	D9	<b>P</b>
0001110	l	0E	·	01000001		41	ll	01110100		74	L	10100111	Į	A7	<b>↓</b>	11011010		DA	<u> </u>
0001111		OF	l	01000010		42		01110101	l	75	<u> </u>	10101000		A8 A9		11011011		DB	+
0010000		10		01000011		43	· · · · · · · · · · · · · · · · · · ·	01110110						A9		11011100			<u> </u>
0010001		11		01000100		44		01110111	· .	77		10101010		AA		11011101		DD	
0010010		12		01000101	<u></u>	45		01111000		78		10101011 10101100		AB		11011110		DE	
0010011		13		01000110		46		01111001		79		10101100				11011111			1
0010100		14		01000111		47	· · · · ·	01111010	:	7A		10101101	· · · · · · · · · · · · · · · · · · ·	AD AE		11100000		E0 E1	4
0010101		15		01001000		48	·	01111011	#	7B		10101111		AE		11100001			
0010110	·	16	·	01001001	ċ	49		01111100	@	7C		10110000		B0		11100010	S T	E2 E3	
00110111		17		01001010		4A 4B		01111101		7D		10110000		BU		11100100		E3 E4	
0011000		18	i	01001011	· <			01111110	.=	7E		10110001		B1 B2			U V	E5	
0011001		19 1A	·	01001100	\$	4C 4D		01111111		7F		10110010		B2 B3		11100101 11100110	w	E6 .	
0011010		1B			+			1000000		80		10110011		B4		11100110	×	E7	
0011100		10		01001110	+	4E 4F		10000001		81 82		10110100		B5		11101000	Ŷ	E8	
0011101		1D		01010000	8	50		10000010	l	82		10110101		86		11101000	Z	E9	
0011110		10 1E		01010000	A A	51		10000100		83	11	10110110	+	B7	I	11101001	2	EA	
00011111	[	1F		01010001		52		10000100		85	<u>├</u> ────┤`	10111000		B7 B8		11101011		EB	
0100000		20		01010010		52		10000101		86		10111000		B8 B9		11101100		EC	+
0100001		21		01010100		54		10000110	t	87	<b>├</b> ────┤	10111010	+	BA		11101101		ED	
0100010		22		01010100		55		10001000		88		10111010	+	BB		11101110		EE EE	
0100011		23		01010101	1	56		10001000		89	<u> </u> ]	10111100		BC		11101111		EF	1
0100100		24		01010111		57		10001010		8A		10111101		BD		11110000	0	FO	
0100101		25		01011000		58		10001011		8B		10111110		BE		11110001	1	F1	
0100110	1	26	11	01011000		59		10001100		8C	t1	10111111	1	BF		11110010	2	F2	
0100111		27	[	01011010	1,	59 5A		10001101		8D		11000000	1	CO		11110010	3	F3	
0101000	t	28		01011010	\$	5B		10001110	t	8E	t1	11000001	A	CI		11110100	4	F4	
0101001	t	29		01011100	*	5C		10001111	<u> </u>	8F	[	11000010	В	C2		11110101	5	F5	
0101010		2A		01011101	1	5D		10010000		90	<u>  </u>	11000011	C.	C3		11110110	6	F6	
0101011		2B	·	01011110	1:	5E		10010001	J	91	<u>                                      </u>	11000100	D	C4		11110111	7	F7	
0101100		2C		01011111		5E		10010010	1	92	11	11000101	E	C5		11111000	8	F8	
0101101		2D		01100000	1.	60		10010011		93		11000110	F	C6		11111001	9	F9	
0101110		2E	·	01100001	17	61		10010100	1	94	t1	11000111	G	C7		11111010	1	FA	1
0101111	1	2F		01100010	1	62		10010100		95		11001000	H.	C8		11111011	1	FB	1
0110000	1	30		01100011	1	63		10010110	1	96		11001001	1	C9		11111100	<u> </u>	FC	1
0110001		31		01100100	1	64		10010111		97		11001010	1	CA		11111101	<u> </u>	FD	1
0110010		32	<u> </u>	01100101		65		10011000	<u> </u>	98	<u>├───</u>	11001011		CB	······	11111110	1	FE	1
		1		1	1		1	1 10011000		1 30		1	1		1 1	11111111	t	FF	+

Hexadecimal numbers of characters in the standard collating sequences.

Where you record the hexadecimal number of the character you are going to put in that relative position in the sequence.

Supplying Sequence Specifications 109

## **Appendix D. Timing Considerations**

The time it takes to run a sort job can vary greatly and is dependent on the following factors:

- The amount of main storage available for the sort program
- Number of records to be sorted
- Record size
- Number of sequence specifications
- Whether alternate collating sequence is being used
- Disk location of the input, work and output files
- Order of control fields in the input file
- Whether or not automatic work file allocation is being used
- Use of nonverify option
- Number of input files and the types of input devices (Model 12 and Model 15)

Here is how each factor affects the length of a sort job.

### MAIN STORAGE SIZE

The more main storage the program has:

- The more sequence specifications you can have
- The longer your records can be
- The faster your sort job will run

See Appendix E for more information and detailed charts.

### NUMBER OF RECORDS TO BE SORTED

The more records you want to sort, the longer the sort job will take. For the most efficient sort job, therefore, use the record omit option whenever possible.

### **RECORD SIZE**

The larger the records, the longer it will take to sort a file. So, if program run time is important to you, do not include fields that contain unnecessary information on your field specifications. (Every field you do not include decreases the record size by the length of that field.) Remember, disk sort builds a work record for each input record included in the sort.

### NUMBER OF SEQUENCE SPECIFICATIONS

The more sequence specifications you use, the less main storage space will be available for records.

- Each sequence specification uses about 25 bytes of storage (remember that comment lines use no main storage).
- The select/build routine uses approximately 100 bytes of storage for functional interfacing.
- If you have specified includes and/or omits (referring to packed data) for your sort run, the select/build routine will use an additional 200 bytes of storage.
- If you have specified field statements (referring to packed data) for your sort run, the select/build routine will use an additional 80 bytes of storage.
- Any alternate collating sequence uses an additional 375 bytes of storage.

But consider using additional sequence specifications to exclude records you do not want to sort. The result may well be a shorter program run than if you use fewer specifications but process more records.

### ALTERNATE COLLATING SEQUENCE

Using an alternate collating sequence increases the time it takes to run a sort job.

### **DISK LOCATION OF THE FILES**

Because the disk sort program must move each record you want to sort two times (first from the input file to the work file and then from the work file to the output file), file location is an important factor in how long it takes to run a job. It is important to minimize the distance the disk arm must travel between the input and work file and between the work and output file. The following diagrams show different ways of locating the input, work, and output files for a sort job.

Within each diagram, the different methods of file placement are shown in order of usual performance characteristics. Each succeeding method will normally run faster than the methods preceding it. For systems having one (or two) 5445 disk storage units available for use with sort, work files should be placed on a 5445 disk storage unit, if possible. If D1 and D2 are both available, put the work file on one drive and the input and output files on the other.

Amount of Main Storage Assigned to Disk Sort <sup>1</sup>	Maximum Recommended Number of Bytes of Select/Build Code			
5K	768			
6K	768			
7K	1024			
8K	1280			
9K	1536			
10K	1792			
11K	2048			
12K	2304			
13K	2560			
14K	2816			
15K	3072			
16K	3328			
17K	3584			
18K	3840			
19K and above	4096			
<sup>1</sup> Maximum storage in the Model 6 is 16K				

5444 File Placement Using one disk on a single drive system

1

2

3

4


5


Input Work Output or Output Work Input Using two disks on a single drive system Work Input R1 Output F1 or I R1 Work F1 Output Input Using three disks on a dual


R1

**R1** 


drive system











*Note:* If the input and output files are on drives separate from the work file, this is optimal file placement. If additional 5445 or 3340 disk drives are available (up to four on Model 15), then much larger files can be sorted and optimal file placement is easier.

### ORDER OF THE CONTROL FIELDS IN THE INPUT FILE

Suppose two files contain identical information; however, some of the first file's records and fewer of the second file's records are in the sequence you want. Using the same sequence specifications to sort each file, disk sort takes less time to sort the first file.

## USE OF THE AUTOMATIC WORK FILE ALLOCATION FUNCTION

Using the automatic work file allocation function generally increases the time needed to run a sort job, because this function does not always provide the work file arrangement needed for a fast sort run. If you are concerned with minimizing sort run-time, use a well planned work file and work FILE statement, rather than automatic work file allocation.

### NONVERIFY OPTION

If an N is entered in column 34 of the disk sort header statement, the disk sort program will not verify data written on the work file. The nonverify option can be used on either a 5444 or 5445 disk pack. The amount of performance improvement depends on file size, number of records, file locations, etc.

Note that when a work file statement is specified for a 3340 file (D1, D2, etc) on Model 15, the verify option is taken from the file statement and column 34 is ignored.

### SAMPLE DISK SORT TIMINGS

The following timings are supplied to aid you in approximating job run times. The sort times shown were generated under the following conditions; any changes may decrease performance:

- Core sizes shown refer to the amount of main storage used by disk sort, excluding the supervisor.
- All timings reflect the total sort run time (generation time plus execution time).

- All runs were made using SORTR, and the record lengths shown reflect input, work, and output record lengths.
- All control fields used were ten characters long.
- All input records were included for minimum select/build generation.
- Alternate collating sequence was not used.
- No alternate track assignments were made.
- Automatic work file allocation was not used.
- Optimal file placement was used for all runs (see *Disk Location of the Files*).

#### Model 6 and Model 10 Timings Only

- Input, work, and output files resided on 5444 Model 2 and 5445 disks for 5444 and 5445 timings, respectively.
- None of the 5445 disks are split cylinder files.
- The input files was overlaid by the output file to minimize file space usage.
- All files were sorted into inverse sequence (from ascending to descending sequence).

#### Model 15 Timings

- Input and output files were on D1; work files were on D2.
- Only one partition was active during the timings.
- All OCL and sort specifications were put on a spool file on D3.
- All files were sorted into descending sequence (from random sequence to descending sequence).

## Sample Model 6 and Model 10 Timings

			Reco	ord Size	
	and the second second	Single	Drive	Dual Drive	
	1	96 bytes	200 bytes	96 bytes	200 bytes
	5K Partition		· · · · · · · · · · · · · · · · · · ·		
	5,000 Records	18 min.	49 min.	11 min.	30 min.
	10,000 Records	34	107	21	62
444	) 12K Partition		1997 - Alexandria		
imings	5,000 Records	7	15	7	11
	10,000 Records	14	31	11	21
	28K Partition				
	5,000 Records	5	8	5	8
	10,000 Records	9	1.7	9	13
2	12K Partition				
	10,000 Records	9	14	9	12
	30,000 Records	32	52	25	33
445	28K Partition			1 A.	
imings	10,000 Records	7	10	7	10
	30,000 Records	17	31	17	26
	44K Partition		1. Sec. 1. Sec		
	10,000 Records	7	9	6	9
	30,000 Records	16	26	15	24

Note: All times are rounded to the nearest minute.

### Sample Model 15 Timings

•		ſ	Rec	ord Size	
		100 byte	S	200 byte	s
	/24K Partition				\
	5,000 Records	3 Min.	38s	4 Min.	56s
i	10,000 Records	5	24	8	28
	20,000 Records	10	1	17	12
Model 15A	50,000 Records	23	23	· - ·	-
5445	(	1.1			1
Timing	48K Partition				
	5,000 Records	3	4	3	47
	10,000 Records	4	28	6	48
	20,000 Records	7	50	11	37
	50,000 Records	19	10	31	25
	/24K Partition				1
	5,000 Records	1	52	2	31
	10,000 Records	3	9	5	18
	20,000 Records	6	17	9	40
Model 15B	50,000 Records	15	53		- 1
and C 3340	ζ ,				1
Timing	48K Partition				1
-	5,000 Records	1	31	1	56
	10,000 Records	2	36	3	43
	20,000 Records	5	3	7	1
	50,000 Records	12	42	18	55
	/ 24K Partition				
	5,000 Records	1	34	2	19 /
	10,000 Records	2	43	4	13
	20,000 Records	5	9	8	42
Model 15D	50,000 Records	13	26	23	14
3340	(				)
Timing	48K Partition				
	5,000 Records	1	21	1 1	48
	10,000 Records	2	16	3	17
	20,000 Records	4	16	6	6 \
	50,000 Records	10	46	16	30 L

*Note:* These sample timings increase in direct proportion to the number of records. For example, using the 5444 (12K partition with a single drive) to sort 7500 96-byte records would take approximately 10 minutes. That is, about 50% more records are being sorted (50% of 5000 = 2500; 2500 + 5000 = 7500) so the sorting time takes 50% longer (50% of 7 = about 3; 3 + 7 = 10).

### Sample Model 12 Timings

Use the sample timings illustrated for Model 15B for a reasonable approximation for the Model 12 run times.

## Appendix E. Calculating Size of Files

### INPUT FILE

Use this formula to calculate how many tracks the input file will require:

### Number of records in the file x input record length

Number of bytes in a track

The number of bytes in a track is 6144 for the 5444, 5120 for the 5445, and 12,288 for the 3340 (Model 12 and Model 15). Round the result up to the nearest whole number.

### **OUTPUT FILE**

Use this formula to calculate how many tracks the output file will require:

Number of records to be sorted x output record length

Number of bytes in a track

The number of bytes in a track is 6144 for the 5444, 5120 for the 5445, and 12,288 for the 3340 (Model 12 and Model 15). Round the result up to the nearest whole number.

*Note:* Number of records to be sorted means the number of records that will be selected to be sorted.

### WORK FILE

Do not use RECORDS to specify the work file, use TRACKS.

Use this formula to approximate how many tracks the work file will require:

 $2 + \left( \begin{array}{c} \text{Number of records to be sorted x} \\ \text{work record length x} \\ \text{approximate work file size factor} \\ \text{Number of bytes in a track} \end{array} \right)$ 

The number of bytes in a track is 6144 for the 5444, 5120 for the 5445, and 12,288 for the 3340 (Model 12 and Model 15). Round the result up to the nearest whole number.

Rather than using this formula to calculate the number of work file tracks needed for each additional run of this job, you can use the actual number of tracks of work file used in this sort. This number is automatically calculated at the end of first pass #0 and is printed out as message SD695. In order to save time, you can use automatic work file allocation for the first run. Then, in subsequent runs, use work FILE statements specifying the number of tracks printed in message SD695.

#### Work Record Length

Type of Sort	Type of Output	Work Record Length
SORTA	Address output	Length of control fields +3
SORTR or SORTRS	Control fields only	Length of control fields as specified in the header line
	Control fields and data	Length of data + length of control fields. (This is the output record length speci- fied in the header line.)
	Data only	Length of data + length of control fields. (Output rec- ord length specified in head- er line plus the control field length specified in header line.)

The following table shows the maximum work record length for a disk sort run, using various combinations of main storage size, input record length, and number of bytes of select/build code. For example, if disk sort is assigned 12K of main storage and your input record length is 1600 bytes, the maximum work record length you can have, using the recommended maximum number of bytes of select/build code, is 2808 bytes. However, if you used fewer than 256 bytes of select/build code in the same situation, you can have a work record length of 3064 bytes. Generally, then, this table shows that for a given amount of main storage, the maximum work record length can be increased by using either fewer bytes of select/build code, or smaller input records, or both. This table can also be used to estimate the maximum input and output block size for tape input/output.

Amount of Main Storage	INPUT RECO	Maximum	
Assigned to Disk Sort	For Jobs with Fewer than 256 Bytes of Select/Build Code	For Jobs with Maximum Recommended Number of Bytes of Select/Build Code <sup>1</sup>	Work Record
	01-768	01-384	760 <sup>2</sup>
<sup>6</sup> К	769-896	385-640	504
	897-1024	641-768	248 <sup>3</sup>
	01-1792	01-896	1784 <sup>2</sup>
	1793-1920	897-1408	1528
	1921-2048	1409-1536	1272
8K	2049-2176	1537-1664	1016
	2177-2304	1665-1792	760
	2305-2432	1793-1920	504
	2433-2560	1921-2048	248 <sup>3</sup>
	01-2176	01-1152	2040
	2177-2304	1153-1664	1784
9K	2305-2432	1665-1792	1528
	2433-2560	1793-1920	1272
	2561-2688	1921-2048	1016
	2689-2816	2049-2176	760
	2817-2944	2177-2304	504
	2945-3072	2305-2432	248 <sup>3</sup>
	01-3200	01-1408	3064
	3201-3328	1409-1920	2808
1	3329-3456	1921-2432	2552
12K	3457-3584	2433-2560	2296
121	3585-3712	2561-2688	2040
	3713-3840	2689-2816	1784
	3841-3968	2817-2944	1528
	3969-4096	2945-3072	1272
	· · · · · · · · · · · · · · · · · · ·	3073-3200	1016
		3201-3328	760
ļ		3329-3456	504
	·	3457-3584	248 <sup>3</sup>
20K and up	01-4096	01-4096	4096
	er of Sequence Specifications ded number of bytes of select,	••	
<sup>2</sup> Not valid f	or SORTRS (summary sort).		

fields for any record type.

Amount of Main Storage	INPUT RECOF	RD LENGTH	Approximate
Assigned to Disk Sort	For Jobs with Less than 11 Sequence Specifications	For Jobs with 11 or More Sequence Specifications	Work File Size Factor
6K	01-768	01-384	1.52
	769-1024	385-768	2.05
	01-1792	01-896	1.17
	1793-1920	897-1408	1.20
	1921-2048	1409-1536	1.25
8K	2049-2176	1537-1664	1.35
	2177-2304	1665-1792	1.52
	2305-2432	1793-1920	2.05
	2433-2560	1921-2048	2.05
<u></u>	01-2176	01-1152	1.15
	2177-2304	1153-1664	1.17
	2305-2432	1665-1792	1.20
9К	2433-2560	1793-1920	1.25
9N.	2561-2688	1921-2048	1.35
	2689-2816	2049-2176	1.52
	2817-2944	2177-2304	2.05
	2945-3072	2305-2432	2.05
· · · · ·	01-3200	01-1408	1.09
	3201-3328	1409-1920	1.10
	3329-3456	1921-2432	1.12
12K	3457-3584	2433-2560	1.13
12N	3585-3712	2561-2688	1.15
	3713-3840	2689-2816	1.17
	3841-3968	2817-2944	1.20
	3969-4096	2945-3072	1.25
		3073-3200	1.35
		3201-3328	1.52
		3329-3456	2.05
		3457-3584	2.05
20K and up	01-4096	01-4096	1.07

118

### EXAMPLE

For this example, assume these values:

Number of records in the file or files (Model 15 only) = 2000

Number of records to be sorted = 1000

Input record length = 200 bytes

Work record length:

SORTA = 13 bytes (control field length = 10) SORTR = 210 bytes (control field length = 10)

Output record length:


SORTA = 3 bytes SORTR = 200 bytes (drop control field)


Main storage size = 8K

Work file size factor = 1.17


Here are the calculations:

### 5444 Disk Files





3340 Disk Files (Model 12 and Model 15)




An alphabetic code helps you judge the significance of each disk sort message:

Code	Meaning	Significance
т	Terminal	The error was destructive. The program must end immediately. No more error messages will be printed.
S	Severe Error	A source statement contains an error. The program ends after the generation phase.
Α	Action	The operator must do something. A system halt follows this message.
w	Warning	An unusual condition has been found. It should be checked out to make sure it did not occur as a result of a programming error.
. 1	Information	For information only. Messages with an I code indicate current status and progress of job.

To understand the messages, you must also know something about how the disk sort program works. Specifically, you must know what happens during the generation phase of the program and what happens during the execution phase.

The generation phase translates your sequence specifications into machine language:



The execution phase gets the records you want sorted, sorts the records, and finally writes the sorted records onto the output file in the order you want them.

 $^{1}\,\mbox{The object program is often referred to as the select/build routine.}$ 

## SD100-ENTER SORT SEQUENCE SPECIFICATIONS-HEADER FOLLOWED BY INCLUDE/OMIT SETS OR // SOURCE NAME, UNIT STATEMENT

Code: Explanation:

System Action:

User Response:

### A-Action

You must tell the system where the sequence specifications for the job are. There are two possibilities: the operator is going to type them on the keyboard (Model 6), on the printer/keyboard (Model 10 or Model 12), or they are already in a source library on one of the disks. System waits for response from operator. If the operator is going to type the specifications on the keyboard (Model 6), or printer/keyboard (Model 10 or Model 12), he or she must follow this sequence:

- 1. Header line
- 2. All the include/omit sets

3. // END

If the sequence specifications are already in a source library on one of the disks the operator types a SOURCE statement. This gives the system the name and disk drive location of the set of sequence specifications.

### SD101-PRINT OPTION ASSUMED TO BE 0

Code:I--InformationExplanation:The print option in your header line is<br/>not blank 0, 1, 2 or 3; therefore, it is<br/>assumed to be 0.System Action:The job continues.User Response:None required.

### SD102-SORT JOB ASSUMED TO BE SORTR

Code: Explanation:	W—Warning Neither SORTA,SORTR, or SORTRS job type is specified on your header line. Because an output record length is speci- fied, SORTR is assumed.
System Action: User Response:	The job continues. Check to make sure that a SORTR job was wanted. To avoid this error the next time the job is run, fill in columns 7-12 of the header line properly.

### SD103-SORT JOB TYPE NOT SPECIFIED

Code:	T—Terminal
Explanation:	Neither a job type nor an output record length is specified in the header line.
System Action:	The job ends.
User Response:	Place the proper job type in columns 7-12 of your header line. Resubmit job.

## SD104–BOTH INPUT AND INPUT1 ARE PRESENT (Model 12 and Model 15)

Code:	S–Severe Error
Explanation:	The filenames INPUT and INPUT1 are
	considered equivalent by disk sort. Only
	one of these filenames may be used in
	a disk sort.
System Action:	The job ends after the generation phase.
User Response:	Eliminate one of the FILE statements
	or change one of the filenames to
	INPUT2, INPUT3,, INPUT8.

### SD105-INPUT FILE NOT ONLINE(Disk Sort only)

Code:	T–Terminal
Explanation:	Pack (or packs) containing the input file is not mounted.
System Action:	Halt 25 occurs for Model 10, Model 12, or Model 15, halt CD45 for Model 6.
User Response:	Mount the pack (or packs) containing the input file. If the input file is multi- volume offline (if more than one pack is assigned to a removable unit), only the first pack assigned to each unit must be mounted. Resubmit the job.

### SD106–WORK FILE NOT ON DISK (Not CCP/Disk Sort)

Code:	T–Terminal
Explanation:	The work FILE statement specifies that
	the work file is to reside on a device other
	than disk, and disk sort requires the work
	file to be on disk.
System Action:	The job ends.
User Response:	Either omit the work FILE statement or
	specify the work file to be on disk. If
	you omit the work FILE statement, disk
	sort automatically allocates your work
	file.

# SD108--INPUT AND/OR OUTPUT FILE STATEMENT MISSING

Code:	T–Terminal
Explanation:	Either the input or output (or both)
	FILE statement is missing in this run.
System Action:	The job ends. The CD45 halt (Model 6)
	or 25 halt (Model 10, Model 12, or
	Model 15) cancels the job.
User Response:	Include missing FILE statement(s) and
	resubmit the job.

### SD109-WORK FILE STATEMENT MISSING

Code:	S-Severe error
Explanation:	A work file was not specified.
System Action:	The job ends after the generation phase.
User Response:	Include the missing FILE statement
	and resubmit the job.

## SD150-CONTROL FIELD DROPPED-NO DATA SPECIFICATIONS

Code:	S-Severe
Explanation:	No data specifications (summary specifica- tions included) were given, yet the control
	field is being dropped. If the sort were
	allowed to continue, the output file would
	be all blanks (X'40').
System Action:	The job ends after the generation phase.
User Response:	Add data field specifications and/or retain
	the control field; then resubmit the job.

## SD151-CONTROL FIELD LENGTH NOT SPECIFIED

T—Terminal
No control field length specified on
header line.
The job ends.
You must place the length of your control
fields in columns 13-17. Do so, and re-
submit job.

## SD152-CONTROL FIELD LENGTH TOO LARGE

Code:	S–Severe error
Explanation:	Control field specified too large; 256 is assumed.
System Action:	The job ends after the generation phase.
User Response:	Make the control field length in columns 13-17 256 or less. Resubmit job.

### SD153-INPUT RECORD LENGTH UNDETERMINABLE

Code:	T–Terminal
Explanation:	The record length of your input file
	cannot be determined from information
	stored on disk.
	CCP/Disk Sort users – Columns 39 and
	40-43 of the header statement did not
	contain an R or C followed by the input
	record length.
System Action:	The job ends.
User Response:	This is a system-program error. If error
	persists, contact your IBM representative
	for program assistance.

# SD154-ASCENDING SEQUENCE ASSUMED A, COLUMN 18

Code:	W—Warning
Explanation:	Column 18 of your header line has
	neither a D for descending, nor an A for
, x	ascending sequence. Disk sort assumes
	you want ascending sequence.
System Action:	The job continues.
User Response:	If you want descending sequence, you
	can cancel the job at the C123 halt
	(Model 6), or at the 22 halt (Model 10,
	Model 12, or Model 15).

## SD155-OUTPUT OPTION ASSUMED X, COLUMN 28

Code:	W—Warning
Explanation:	Column 28 of your header line is neither an X nor blank.
System Action:	Disk sort assumes you want an X in column 28 and continues the job.
User Response:	If you do not want X, you can cancel the job at the C123 halt (Model 6), or at the 22 halt (Model 10, Model 12, or Model 15).

## SD156-OUTPUT RECORD LENGTH NOT SPECIFIED

Code: Explanation:	S-Severe error This is a SORTR or SORTRS job. Out- put record length not specified on header line. Disk sort assumes you want the maximum length of 4096.
System Action: User Response:	The job ends after the generation phase. Enter an output record length in columns 29-32 of your header line and resubmit the job.

## SD157-OUTPUT RECORD LENGTH TOO LARGE

Code:	S-Severe error
Explanation:	This is a SORTR or SORTRS job. Out- put record length specified on header line is too large. Disk sort assumes you
	want the maximum length of 4096.
System Action:	The job ends after the generation phase.
User Response:	Make sure your header line is not shifted by one or more columns. Specify on out- put record length of 4096 or less and re- submit job.

### SD158-OUTPUT RECORD LENGTH INCONSISTENT

Code:	S-Severe error
Explanation:	This is a SORTR or SORTRS job and
	you are not dropping the control field.
	Consequently, the output record length
	(Columns 29-32) that includes the con-
	trol field should not be less than the con-
	trol field (columns 13-17).
System Action:	A length equal to that in columns 29-32
	plus the largest total control field (col-
	umns 13-17) is assumed.
User Response:	Recompute your output record length,
	change it on your header line, and resub-
	mit the job.

## SD159-WORK RECORD LENGTH TOO LARGE

Code:	S–Severe error
Explanation:	Disk sort's work record exceeds the
	maximum length allowed.
System Action:	Halt CD45 (Model 6) or halt 25 (Model 10,
	Model 12, or Model 15) occurs.
User Response:	Refer to Appendix E to determine the
	maximum work record length.

# SD160-ALTERNATE COLLATING SEQUENCE ASSUMED

Code:	W—Warning
Explanation:	Columns 26 is neither an S nor blank.
System Action:	Disk sort assumes you want an alternate
	collating sequence and continues the job.
User Response:	If you do want an alternate collating
	sequence, put an S in column 26 of your
	header line before running the job again.
	If you do not want an alternate collating
	sequence, you can cancel the job at the
	C123 halt (Model 6) or the 22 halt (Model
	10, Model 12, or Model 15).

## SD161-INVALID NUMBER IN CONTROL FIELD

Code:	T—Terminal
Explanation:	There is either a nonnumeric character or
	embedded blank in columns 13-17 of the
	header line.
System Action:	The job ends.
User Response:	Correct the mistake and resubmit the job.

# SD162-INVALID NUMBER IN OUTPUT RECORD LENGTH

Code:	T–Terminal
Explanation:	There is either a nonnumeric character
	or embedded blank in columns 29-32
	of the header line.
System Action:	The job ends.
User Response:	Correct the mistake and resubmit the job.

# SD163-SORTA-TAPE OUTPUT, RECORD LENGTH NOT 18

Code:	T–Terminal
Explanation:	The record length on the output FILE
	statement is not 18.
System Action:	The job ends.
User Response:	For a tape output file during a SORTA
	(addrout) sort, the record length on the
	output FILE statement must be 18.

SD164—SORTA—MULTIPLE INPUTS (Model 12 and CCP/Disk Sort)

Code:	S—Severe error
Explanation:	Addrout sort is invalid with multiple disk or tape files.
System Action: User Response:	The job ends after the generation phase. Modify your OCL to perform an addrout sort on a single disk or tape file, or merge all the files into a single file before performing an addrout
	sort.

## SD164-SORTA-CARD, 3741, OR MULTIPLE INPUT (Model 15 only)

Code:	S–Severe error
Explanation:	Addrout sort is invalid with card input,
	3741 input, or multiple disk or tape files.
System Action:	The job ends after the generation phase.
User Response:	Modify your OCL to perform an addrout sort on a single disk or tape file, or merge
	all the files into a single file before per-
	forming an addrout sort.

### SD165-SORTA-ASCII TRANSLATE SPECIFIED

Code:	T–Terminal
Explanation:	If the addrout file is converted to ASCII,
	the result is an unusable file.
System Action:	The job ends.
User Response:	ASCII translate must not be specified if a
	tape addrout file is desired.

SD166-VERIFY OPTION ASSUMED BLANK, COLUMN 34

Code:	W–Warning
Explanation:	Column 34 of the header does not contain
	an N or a blank. Disk sort will continue the sort, and assume that you meant for
	column 34 to be blank. Therefore, any writes to the work file will be verified.
System Action:	Disk sort assumes that you want any writes to the work file to be verified.
User Response:	If you desire not to have all writes to
	the work file verified, you must code an N in column 34 and rerun the job.

### SD167-INVALID STORAGE SIZE TO EXECUTE

Code:	W–Warning
Explanation:	The entry in columns 37-38 was:
	1. Blank or nonnumeric
	2. Less than 12
	3. Greater than 48
	4. Not a multiple of 2
System Action:	For the above cases, the following
	defaults occur:
	- For items 1 and 2, 12 is assumed.
	- For item 3, 48 is assumed.
	- For item 4, the value is rounded down
	to the next lowest multiple of 2.
User Response:	If the default is not acceptable, enter
	the proper value and resubmit the job.

### SD168-MISSING OR INVALID PROGRAM NAME

Code:	W-Warning
Explanation:	The entry in columns 75-80 of the header
지 않는 말을 했다.	statement is either blank or has an invalid
	program name.
System Action:	The program name defaults to SRTOBJ.
User Response:	If the default is not acceptable, enter the
	correct program name in columns 75-80
	and resubmit the job.

# SD169-MIXED EBCDIC AND ASCII FILES (Model 10 only)

Code:	S–Severe
Explanation:	The job is attempting to mix ASCII and
	EBCDIC input and output files. Both
	input and output files must be the same type of data.
System Action:	The job continues through the generation
	phase to diagnose the sort sequence
	specifications but terminates at the end
	of the generation phases.
User Response:	Translate mixed files so they are the
	same type (ASCII or EBCDIC). For
	example, if you have EBCDIC input and
	you desire ASCII output, translate the
	input to ASCII, then run the sort job.

### SD172-7-TRACK OUTPUT-SORTA TYPE SORT

Code:	S–Severe error
Explanation:	The output of a SORTA (addrout) sort is
	a 3-byte relative record number. Binary
	output from a SORTA sort cannot go on
	a 7-track tape.
System Action:	The job ends after the generation phase.
User Response:	When a SORTA sort is desired, output

## SD173-CONVERIOR OR TRANSLATOR NOT SPECIFIED

Code:	S—Severe error
Explanation:	Either the convertor or translator must be specified on the FILE statement if an in-
	put or output file is on 7-track tape.
System Action:	The job ends after the generation phase.
User Response:	Specify either convertor or translator on
	the FILE statement of the input or out-
	put file that is on 7-track tape.

## SD176-INVALID ALTERNATE SEQUENCE STATEMENT

Code:	S–Severe error
Explanation:	You specified an alternate sequence in
	column 26 of your header line. The statement just read does not have
	ALTSEQ66 in columns 1-8. Also it is
	not a comment statement or a valid sort
	specifications statement.
System Action:	The statement is ignored, and the job ends after the generation phase.
	enus arter the generation phase.
User Response:	If the statement does not belong in the
	job, delete it. If it does belong in the
	job, correct it.

## SD177-MISSING THE \*\* STATEMENT

Code:	W–Warning
Explanation:	Disk sort has read the ALTSEQ state-
	ments specified in column 18 of your
	header line. An ** (columns 1-2) state-
	ment should follow the last ALTSEQ
	statement that precedes your include/
	omit/field sort specification statements
	(I/O/F in column 6). However, the
	statement just read was an I/O/F
	statement.
System Action:	Disk sort assumes an ** statement before
	the I/O/F statement.
User Response:	Place an ** before the I/O/F statement
	before rerunning the job.

## SD178-ALTSEQ STATEMENT HAS INVALID DATA

Code: Explanation:	S—Severe error The data to alter the normal sequence in the above ALTSEQ statement is in error. One of the 4-position groups (columns 9-12, 13-16, etc.) does not contain a valid hex number (0-9 or A-F).
System Action:	The column(s) in error have been flagged with an * in the line printed above this message. Processing continues with the next 4-position group. The job ends after the generation phase.
User Response:	Correct the statement and resubmit the job.

### SD179-UNEXPECTED END-OF-FILE FOUND

Code:	TTerminal
Explanation:	Disk sort was reading your ALTSEQ
	statements. Valid statements following
	an ALTSEQ statement are: another
	ALTSEQ statement, a comment statement,
	or an ** statement (columns 1-2). How-
	ever, disk sort found an end-of-file state-
	ment. (If your sequence specification
	statements are being read from the system
	reader, the program read a /*, /&, or //
	END statement.)
System Action:	Job ends at this point. No further state- ments are diagnosed.
User Response:	Make sure the last part of your sequence
	specifications are not missing.

### SD181-NO VALID ALTSEQ STATEMENTS FOUND

Code: Explanation:	W—Warning ALTSEQ is specified on the header line, but the system cannot find any valid ALTSEQ statements.
System Action:	There will be no alternate collating sequence for this job; processing continues.
User Response:	If you want an alternate collating sequence, cancel the job at halt C123 (Model 6) or halt 22 (Model 10, Model 12, or Model 15), correct the ALTSEQ statements, and resubmit the job. If you do not want an alternate collating sequence, remove the S from column 26 of your header line.

### SD202-INVALID SPECIFICATION TYPE, COLUMN 6

Code:	S—Severe error
Explanation:	The statement makes no sense to disk sort because it is not a comment statement, an include statement, an omit statement, or a field statement.
System Action:	Disk sort bypasses the statement. The job ends after the generation phase.
User Response:	This statement is either misplaced or in- correctly typed. Correct the statement and resubmit job.

## SD204-BLANK CONTINUATION ASSUMED, COLUMN 7

Code:	W–Warning
Explanation:	The referenced statement is the first in an omit or include set. However, it con-
	tains a nonblank character in column 7.
	A blank was expected.
System Action:	Disk sort ignores the nonblank character
	and processes the statement as though
· · · ·	column 7 was blank.
User Response:	Correct statement before next job run.

### SD206-INVALID CONTINUATION, COLUMN 7

Code:	S-Severe error
Explanation:	The referenced statement is part of an
	include or omit set. It should have an A
	(AND) or O (OR) in column 7. However,
	it does not, nor does it contain a blank
	(see message SD208).
System Action:	Disk sort bypasses the statement and
	goes on to the next statement. Job will
	terminate at end of generation phase.
User Response:	Correct the statement before running the
	job again.

## SD208-OR CONTINUATION ASSUMED, COLUMN 7

Code:	W–Warning
Explanation:	The referenced statement is part of an include or omit set. It should contain an
	A (AND) or O (OR) in column 7. How- ever, column 7 is blank.
System Action:	Disk sort assumes you want an O in column 7.
User Response:	Check the order of your statements. Make sure you want an O in column 7. If you do not, you can cancel the job at the C123 halt (Model 6) or the 22 halt (Model 10, Model 12, or Model 15).

## SD210-INVALID C/Z/D/P/U/V SPECIFICATION, COLUMN 8

Code: Explanation:	W–Warning Type of Statement	Column 8 Entry Should Be:
	Include or omit record type	C, Z, D, P, or U
	Control field statement <sup>1</sup>	C, Z, D, P, or U
System Action:	Data field or summary field Disk sort assumes you 8.	C, Z, D, U, P or V u want a C in column
User Response:	Check the character i correct the statement this job.	

<sup>1</sup> For an unconditional force or a force-all line, the column 8 entry must be a C.

### SD212-SPECIFICATION IN WRONG LOGICAL ORDER

Code:	S–Severe error
Explanation:	If this is a control field statement (F in column 6), it improperly follows an omit statement (O in column 6). If this is an
	omit statement, it improperly follows an include statement (I in column 6).
System Action:	This statement is bypassed and processing continues with next statement. The job ends after the generation phase.
User Response:	Put your statement in proper order and resubmit the job.

## SD214-INCLUDE OR OMIT STATEMENT AFTER INCLUDE-ALL

Code:	S–Severe error
Explanation:	Disk sort has previously read an include-
	all statement. Now only control field
	statements (F in column 6) should be
	read. However, an include or omit (I
	or O in column 6) was just read.
System Action:	This statement and all following state-
	ments are processed as though the include-
	all card had not been read. The job ends
	after the generation phase.
User Response:	Remove either the include-all statement
	or the include or omit statement. Resub-

### SD216-LAST SET NOT A VALID INCLUDE SET

mit job.

Code: S-Severe error Explanation: The last set of your sequence specifications should have been an include set. However, one of the following types of errors occurred:

- 1. There were no statements after the header statement.
- 2. The last set was an omit set.
- 3. The last set was an include set, but it contained no field statements.
- System Action: The job will terminate at the end of the generation phase.

User Response: Make one of the following corrections depending upon the type of error that occurred:

- 1. Supply the sequence specifications.
- 2. Eliminate this omit set, because the records are omitted by default.
- 3. Supply the missing field statements. Resubmit the job.

### SD218-TOO MANY SEQUENCE SPECIFICATIONS

Code:	S–Severe error
Explanation:	You have used all the main storage that was allocated by disk sort for the select/build routine and for error information.
System Action:	Disk sort reads and error checks any
	following statements, but the job ends after the generation phase. The area allocated for the select/build routine and error information is now used only for error information.
User Response:	Remove all causes of error messages. If this error occurs with no other error messages, decrease the number of sequence specifications.

### SD220-TOO MANY ERRORS

Code:	T–Terminal
Explanation:	The main storage that disk sort allocated for the select/build routine and error in- formation is now filled with error infor-
	mation (see message SD218).
System Action:	Disk sort will not read or diagnose any more statements. The job ends at this point.
User Response:	If your statements are being read from the system card input device, make sure you've included /* and /& statements.

### SD222-ZONE OR V FIELD-LENGTH EXCEEDS 1

	and the second
Code:	W-Warning
Explanation:	The referenced statement is a field state-
	ment (F in column 6). The type specified
	is a zone field (Z in column 8) or a V field
	(V in column 8) which should have a
	length of one byte.
System Action:	The specified number of bytes (calculated
	using columns 9-12 and 13-16) is used in
	building the work record field for this
	record type. The byte of zone or overflow
	information generated is placed in the
	rightmost byte (low order byte) of this
	field. The other positions to the left con-
	tain binary zeros (control fields) or blanks
	(data fields).
User Response:	If you do not want a length of one byte,
2000 - 100 -	respond to the C123 halt (Model 6) or
	the 22 halt (Model 10, Model 12, or
	Model 15) with a controlled cancel (op-
	tion 2). The Halt Guide for each system
	lists all the halts and the options for each

one.

### SD224-COLUMNS 9-16 OR COLUMNS 20-27 ARE INVALID

Code:	S–Severe error
Explanation:	The location information in columns
	9-16 and/or columns 20-27 of the refer-
	enced statement is invalid for one of these
$\sim 10^{-10}$	reasons:
	1. The from location is greater than
	the to location.
	2. The to location is blank or zero.
	3. The lengths of factor 1 and factor
	2 are not the same.
System Action:	The job ends after the generation phase.
User Response:	Correct this statement and resubmit the
	job.
SD226-DIGIT I	FIELD LENGTH EXCEEDS 16
Code:	W—Warning
Explanation:	A digit field longer than 16 bytes has been
1.4	specified in the referenced statement.
System Action:	Disk sort assumes you want a length of
	16. The job ends after the generation
	phase.
User Response:	If your digit field is longer than 16 bytes,
	divide it into two or more fields. Create

divide it into two or more fields. Create new specifications for these fields and resubmit job. If your digit field is really 16 bytes or shorter, correct the statement and resubmit the job.

SD228-CHARACTER CONSTANT-LENGTH EXCEEDS 20

W-Warning
The referenced statement is an include or omit statement (I or O in column 6). Factor 2 contains a character constant since column 19 contains a C. The length implied in factor 1 (columns 9-12 and
13-16) is greater than 20, which is the maximum length allowed.
The rightmost 20 columns in factor 1 will be compared against the constant in columns 20-39.
If you do not want a 20-byte field you can end the job after the generation phase at the C123 halt (Model 6) or the 22 halt (Model 10, Model 12, or Model 15).

### SD230-SAME SPECIFICATION TYPE ASSUMED, COLUMN 6

	1
Code:	W-Warning
Explanation:	The referenced statement has a blank in column 6, so the specification type is not known. However, column 7 of this state- ment contains an A or O. The previous statement was either an include or omit statement (I or O in column 6).
System Action:	Disk sort assumes the statement is a rec- ord type one with a specification type identical to that of the previous state- ment; that is, include (I) or omit (O).
User Response:	If the statement is not a record type state- ment, you can cancel the job after the C123 halt (Model 6) or the 22 halt (Model 10, Model 12, or Model 15). In either case, correct the statement before re- running the job.

### SD232-ZONE SPECIFIED-FACTOR 2 IS NOT A CONSTANT

Code:	S–Severe error
Explanation:	A zone was specified in column 8 of a record type statement (include or omit) and column 19 does not have a C (con-
	stant) specified.
System Action:	Disk sort bypasses the statement. The job ends after the generation phase.
User Response:	Correct the statement and resubmit the job.

SD234-ZONE SPECIFIED-RELATIONSHIP NOT EQ OR NE

Code:	W–Warning
Explanation:	A zone has been specified in column 8 of
	the referenced record type statement (in-
	clude or omit) and columns 17-18 do not contain EQ or NE.
System Action:	Disk sort assumes you want EQ in columns
	17-18; processing of this statement continues.
User Response:	If you do want an EQ in columns 17-18,
	you can continue the job after the C123
	halt (Model 6) or the 22 halt (Model 10,
	Model 12, or Model 15). Correct the
	column 17-18 entry in the statement
	before the next job is run.

### SD236-INVALID RELATIONSHIP, COLUMNS 17-18

Code:	S-Severe error
Explanation:	The referenced statement is a record type statement (include or omit) and columns 17-18 (the relationship between factor 1
	and factor 2) does not contain an EQ,
	NE, LT, GT, LE, or GE.
System Action:	System assumes an EQ entry in columns
	17-18. The job ends after the generation phase.
User Response:	Correct statement and resubmit job.

### SD238-INVALID FACTOR 2 TYPE, COLUMN 19

Code:	W-Warning
Explanation:	The referenced statement is a record type specification (include or omit) and column 19 contains neither an F (field) nor C (constant).
System Action:	Column 19 is assumed to contain a C; factor 2 is taken as a constant.
User Response:	Check column 19 for an invalid character or missing character. If you do not want a C in column 19 you can cancel the job after the C123 halt (Model 6) or the 22 halt (Model 10, Model 12, or Model 15). In any case, you should correct the statement before running the job.

## SD240-UNPACKED DECIMAL-LENGTH EXCEEDS 16

Code:	WWarning
Explanation:	The referenced statement has a U in
	column 8. Columns 8-12 and 13-16
	specify a factor 1 field longer than the
	allowable maximum of 16 bytes.
System Action:	Disk sort processes the statement with a
	length of 16. The job ends after the
	generation phase.
User Response:	Check the to and from columns and
	correct the statement before resubmitting
	job.

### SD242-ZONE SPECIFIED-LENGTH EXCEEDS 1

Code:	W–Warning
Explanation:	The referenced statement is a record type
	specification (include or omit) with a Z
	(zone) in column 8. Factor 1 must be only
	one character long and it was not.
System Action:	A length of 1 is assumed. Column 20 in
	this statement contains the constant that
	will be processed.
User Response:	Verify that the assumption is correct. If
	it is not, you can cancel the job after the
	C123 halt (Model 6) or the 22 halt (Model
	10, Model 12, or Model 15). In any case,
	you should correct the statement before
	rerunning the job.

## SD244-PACKED DECIMAL-LENGTH EXCEEDS 8

Code:	W–-Warning
Explanation:	Field length excessive. The P (packed)
an an an an Arta an Arta. An an Arta an Arta an Arta an Arta an Arta	in column 8 dictates that the field must
	be only eight columns long (15 digits plus sign).
System Action:	The specified number of bytes (calculated from columns 9-12 and 13-16) are used in building the work record field for this
	record type. Eight bytes of input
	information are used; the remainder of
	the field is unpredictable. The
	rightmost eight bytes of the field are used
	for include or omit. If column 19 contains
	a C, the constant in columns 20-35 of this
	statement is used for factor 2.
User Response:	If you do not want to accept disk sort's
	assumptions, you can cancel the job after
	the C123 halt (Model 6) or the 22 halt
	(Model 10, Model 12, or Model 15).
	In any case, you should correct the
	statement before running the job again.

# SD246-INVALID FIELD TYPE SPECIFICATION, COLUMN 7

Code:	W–Warning
Explanation:	The referenced statement is a field specifi-
	cation; however, column 7 does not con-
	tain an F, N, O, D or S.
System Action:	The referenced field statement will be
	assumed as an N (normal control field)
	if there have been no previous data or
	summary data field specifications for
	this include set. Otherwise it will be
	assumed to be a D (data field) specification.
User Response:	If you do not want an N in column 7, you
	can cancel the job after the C123 halt
	(Model 6) or the 22 halt (Model 10,
	Model 12, or Model 15). In any case,
	you should correct the statement before
	running the job again.

## SD248-ILLEGAL FORCE-ALL CONTINUATION

Code:	S-Severe error
Explanation:	The referenced statement is a field state-
	ment for a force-all specification (F in
	column 7). However, it does not follow
	a conditional force specification as it
	should.
System Action:	Disk sort ignores the statement. The job ends after the generation phase.
User Response:	Correct statement and resubmit job.

# SD250-FIELD STATEMENTS IN WRONG LOGICAL ORDER

S-Severe error
The referenced statement is a control
field specification. However, a data (D)
or summary (S) specification was previous-
ly specified in this include set. All control
field statements (N, O, or F in column 7) must precede any data or summary data
field specifications.
The statement is bypassed. Processing continues with next statement. The job ends after the generation phase.
This statement is either misplaced or in- correctly specified. Correct the statement and resubmit the job.

# SD252-CONTROL FIELD LENGTH EXCEEDS HEADER VALUE

Code:	S-Severe error
Explanation:	The accumulated length of control field statements within the current include set exceeds length specified in header statement.
System Action:	Disk sort processes all the following state- ments in this include set but the job ends after the generation phase.
User Response:	Check the length specified in header line against the specified control fields. Correct the errors and resubmit job.
	against the specified control fields.

# SD254-CONTROL FIELD LENGTH LESS THAN HEADER VALUE

Code: Explanation:	W-Warning The accumulated length of control fields specified for this include set is less than length specified in header statement.
System Action:	All control field statements have been processed for this include set. The re- maining positions are filled with binary zeros.
User Response:	You can continue the job after the C123 halt (Model 6) or the 22 halt (Model 10, Model 12, or Model 15). Check control field length in header line before running

# SD256-CHARACTER FIELD SPECIFICATION-LENGTH EXCEEDS 256

the job again.

Code:	S–Severe error
Explanation:	The referenced statement is a character field specification (C in column 8). A
	length of more than 256 has been specified on this statement.
System Action:	The job continues through the generation phases to diagnose the sort sequence specifications but terminates at the end of the generation phases.
User Response:	If you require more than 256 positions of data, split the field into more than one field specification statement.

# SD258-TO OR FROM FIELD NOT WITHIN INPUT RECORD

Code:	S-Severe error
Explanation:	Either or both specifications in the to
	or from columns are zero or contain a
	value larger than your input record length.
System Action:	This job ends after the generation phase.
User Response:	Check to make sure you have the desired
	input file. Also check that the from and
	to columns contain the desired values.

## SD262-DATA LENGTH EXCEEDS HEADER VALUE

•	Code: Explanation: System Action: User Response:	S-Severe error The data field specifications (columns 6 and 7 contain FD or FS) for this include set now exceed your data length value. A SORTR or SORTRS job was specified. If you are dropping the control field (column 28 of the header line contains an X), the data length is the output record length (columns 29-32 of the header line). If you are not dropping the control field, the control field length (columns 13-17 of the header line) must be subtracted from the output record length to get the data field length. The job ends after the generation phase. There is an error in either the output record length in header line or the to and from fields in the field description lines. Correct the error and resubmit the job.
	SD264—SPECIF ORDER	ICATIONS IN WRONG NUMERICAL
	Code:	W–Warning
	Explanation:	Columns 1-5 of each sequence specifica- tion statement are used to order the state- ments. One or more of the statements has a value in columns 1-5 that is less than the preceding statement. Disk sort prints an S to the left of the statements that are out of order.
	System Action:	Disk sort assumes the specification state- ments are in the order you want.
	User Response:	Check the order of the sequence specifica- tions. If they are out of order, respond to the C123 halt (Model 6) or the 22 halt (Model 10, Model 12, or Model 15) with option 2. (The Halt Guide for each system explains the options fol-

lowing each halt.)

Messages 133

### SD266-FACTOR 1 LENGTH EXCEEDS 256

Code:	S–Severe error
Explanation:	The referenced statement is an include or omit specification for character data (column 8 contains a C). Factor 1 is a
	field (column 19 contains an F). The length of factor 1 exceeds 256 bytes.
System Action:	Disk sort assumes a factor 1 length of 256 but ends the job after the generation phase.
User Response:	Break this statement into two specifica- tions with an AND continuation line (put an A in column 7).

### SD268-P OR U FACTOR 1 USED WITH ALTSEQ

Code:	W-Warning
Explanation:	The referenced include or omit record type statement specifies a packed or unpacked factor 1 and an alternate collat- ing sequence is specified in the header statement.
System Action:	Factor 1 and factor 2 are changed as in- dicated by the ALTSEO statements. This change may affect the units position (and sign) of an unpacked decimal number or any one position of a packed decimal number. If it does, you may not include or omit the desired records.
User Response:	Do not use P or U column 8 record type entries when you specify an alternate collating sequence.

## SD269—PACKED FIELD USED WITH 96-COLUMN INPUT (Model 15 only)

Code:	W—Warning
Explanation:	96-column cards can contain only the
	System/3 64-character set. Packed data
	cannot be contained on a 96-column card.
System Action:	A 22 halt is issued at the end of the generation phase.
	<b>.</b>
User Response:	Verify that you are not trying to retrieve
	packed data from a 96-column card. The use of include sets may be necessary when
	using 96-column card input.

## SD270-INVALID SPECIFICATION WITH TRANSLATE ON

Code: Explanation:	S—Severe error If input is on 7-track tape with TRANS- LATE-ON, include, omit, or field specifica- tions with packed data are not allowed.
	If output is on 7-track tape with TRANS- LATE-ON, field specifications with packed data are not allowed.
System Action:	The job ends after the generation phase.
User Response:	Either correct the invalid specifications, change the output file to a 9-track tape file, or change the input file to a 7-track tape file with CONVERT-ON specified.

# SD271-INVALID SPECIFICATION UNLESS CONTROL FIELD DROPPED

Code:	S–Severe error
Explanation:	The control field is a normal packed or unpacked field, or an opposite packed, unpacked, zone, or character field. All of these control fields are modified by the disk sort program and will contain meaningless data.
System Action:	The program ends after the generation phase.
User Response:	Indicate that the control field is to be dropped (code an X in column 28 of the header statement) and repeat (as a data field) any of the control fields you want in the output record.

## SD276-MORE THAN ONE SUMMARY V FIELD IN INCLUDE SET

Code: Explanation:	W-Warning This is a SORTRS job. The referenced statement specifies a summary V field (FSV in columns 6-8). At least one other summary V field has already been speci- fied for this include set.
System Action:	A data V field is assumed (FDV in columns 6-8).
User Response:	Change the extra summary V field(s) to data V fields before running the job again.

### SD278-SUMMARY V OR DATA FIELD INCONSISTENT

Code: W-Warning This is a SORTRS job. The referenced Explanation: statement is a summary data field specification (S in column 7). Compare this specification with the first include set having S specifications; one of the following is true: The number of S specifications prior • to this specification differs. • The length of this S specification differs. The substitution character of this V specification differs. • The relative location of the specification within the output record differs. System Action: The S specifications of the first include set having S specifications are used to actually define the summary field positions. User Response: A C123 halt (Model 6) or a 22 halt (Model 10, Model 12, or Model 15) will occur at the end of the Generation Phase. Check carefully to assure that the first include set with S specifications is correct. If not, correct and take a 2-option (controlled cancel).

## SD280-NUMBER OF SUMMARY FIELDS INCONSISTENT

Code:	W-Warning
Explanation:	This is a SORTRS job. The total number
	of S specifications in this include set
	differs from the first include set having
	an S specification.
System Action:	The S specifications of the first include
	set having S specifications are used to
	actually form the summary output
	records.
User Response:	A C123 halt (Model 6) or a 22 halt (Model
	10, Model 12, or Model 15) will occur at
	the end of the generation phase. Check
	carefully to assure that the first include
	set with S specification is correct. If not,
	correct and take a 2-option (controlled
	cancel).

### SD282-NO SUMMARY SPECIFICATIONS FOUND-SORTRS JOB

Code: Explanation:	W-Warning A SORTRS job (summary tag along sort) was specified on the header statement for this job. However, no summary data field specifications were found in the
C	statements for this job.
System Action:	All records with duplicate control fields will be eliminated from the output file.
User Response:	Check the job type to be sure that SORTRS was intended.

### SD284-SUMMARY SPECIFICATIONS FOUND-SORTR JOB

Code: Explanation:	W–Warning This is a SORTR job. A summary data field specification (columns 6 and 7 con- tain FS) is expected only for SORTRS
	jobs. At least one S specification was found for this job.
System Action:	All S specifications are treated as data specifications (column 7 contains a D rather than an S).
User Response:	Check to assure that a SORTRS job was not wanted.

## SD286-TOO MANY SUMMARY DATA FIELDS

Code:	S-Severe
Explanation:	This is a SORTRS job. More than 24
	summary data fields (FS in columns 6
	and 7 and C, D, P, or U in column 8) have
	been specified.
System Action:	The job will end after the generation phase.
User Response:	Limit the number of summary data fields
	to 24 or less.

## SD288-INVALID SORTRS SPECIFICATION-COLUMNS 20, 21, 22

Code:	W—Warning
Explanation:	The overflow field length in columns 20-
	22 is invalid, not right-justified, or less
	than the field length given by to and from entries for this specification.
System Action:	Disk sort assumes that no entry was made in columns 20-22.
User Response:	If a valid entry was meant for columns
	20-22, cancel the job (C123 Halt–Model
	6 or 22 halt—Model 10, Model 12, or
	Model 15), correct entries, and rerun
	the job. If no entry was meant for
	columns 20-22, the job will run but
	warning message will continue until
	error is corrected.

# SD301-TAPE VARIABLE LENGTH BLOCK SPECIFIED

Code:	T–Terminal
Explanation:	Variable length blocks are not allowed on input files. Your input FILE statement is incorrect.
System Action:	The job ends.
User Response:	Disk sort accepts only fixed length block files from tape. Specify fixed block files on the FILE statement.

# SD302-RECL AND/OR BLKL NOT SPECIFIED

Code:	T—Terminal
Explanation:	RECL and BLKL must be specified for a
	tape file on the FILE statement.
System Action:	The job ends.
User Response:	Specify RECL and BLKL and resubmit the job.

# SD303—HEADER AND TAPE OUTPUT LENGTH DISAGREE

Code:	T—Terminal
Explanation:	The output record length specified on the output FILE statement and the output
	record length specified on the sort header statement are not the same.
System Action:	The job ends.
User Response:	Both record lengths (output FILE state- ment and sort header statement) must agree.

# SD391-MAIN STORAGE ALLOCATED TOO SMALL

Code: Explanation:	TTerminal The amount of main storage assigned to disk sort is not large enough to handle the job. On the Model 15, this halt can occur if the system was not generated with the support needed for a particular device such as tape, 5445, or card support. For CCP/Disk Sort, this occurs when the
	work record length is less than three bytes. This halt can also occur when a CCP/Disk Sort module is missing from the pack on which the CCP/Disk Sort resides.
System Action:	This sort job cannot run. The CD45 halt (Model 6) or 25 halt (Model 10, Model 12, or Model 15) cancels the job.
User Response:	Make sure you have the right input file. Check the SORTR or SORTRS output length specified in your header line if this is a tag along sort. Also check that the total number of bytes reserved for the sequence specifications (message SD461) does not exceed the recommend- ed amount (see Appendix D). In addition, make sure there are no entries in positions 35-39 of the header statement (reserved for system use).

For CCP/Disk Sort, if the work record length is less than three bytes, then increase the control field record length or the output record length.

Ensure that all the CCP/Disk Sort modules are on the pack.

# SD395-NOT ENOUGH SPACE FOR WORK FILE

Code:	TTerminal	Cod
Explanation:	Disk sort automatic work file allocation	Exp
	is being used. One or more of the follow-	
1. 1. 1. 1. 1. 1. 1. 1. 1. 1. 1. 1. 1. 1	ing situations has occurred:	
	1. The disk packs that are currently	Syst
	online cannot be used for work	User
	space because they contain multi-	
	volume offline files or because a de-	
	ferred mount is requested.	
	2. No work space is available on the	
	online disk packs.	
	3. No work space is available on the	
	disk packs indicated on the SWITCH	
	statement (Model 12 and Model 15).	
System Action:		
	To make more scratch space available,	
	perform one of the following:	
	1. Delete unnecessary files on the on-	
	line disk packs (preferably the fixed	
	units).	
<i>x</i>	2. Mount a removable pack that has	
	enough scratch space available.	
a di ya	3. Remove or modify the SWITCH	

. Remove or modify the SWITCH statement (Model 12 and Model 15).

# SD398-WORK FILE EXTENTS NOT USEABLE

Code:	T—Terminal
Explanation:	None of the track extents specified on the work FILE statement are large enough for a work block.
System Action: User Response:	Increase the number of tracks on the work FILE statement so that the extents
	will be large enough to hold a work block.

## SD401–JOB COMPLETED GENERATION PHASE

Code:	I-Information
Explanation:	This job has completed the generation
	phase. All diagnostics have been checked
	for errors.
System Action:	If severe errors were found, message SD425
	and halt CD45 (Model 6) or halt 25 (Model
	10, Model 12, or Model 15) follow. If
	warning errors were found message SD422
	and halt CD123 (Model 6) or halt 22
	(Model 10, Model 12, or Model 15) follow.
	If no errors were found, the job proceeds
	to the execution phase of disk sort.
User Response:	Review subsequent messages.

#### SD402-NO ERRORS FOUND

Code:	I-Information
Explanation:	No errors were found in the generation phase of disk sort.
System Action:	Processing continues to the execution phase.
User Response:	None.

# SD403-OPERATOR CHOSE TO CANCEL JOB

Code:	I-Information
Explanation:	Message SD422 with halt CD123 (Model
	6) of halt 22 (Model 10, Model 12, or
	Model 15) was just given. The warn-
	ing error was not expected, so the operator
	chose to cancel the job.
System Action:	Processing ends.
User Response:	Correct the errors and resubmit the job.

# SD404-OPERATOR CHOSE TO CONTINUE JOB

Code: Explanation:	<ul> <li>I—Information</li> <li>Message SD422 with halt CD123 (Model</li> <li>6) or halt 22 (Model 10, Model 12, or</li> <li>Model 15) was just given. The warning</li> <li>errors were expected, so the operator</li> </ul>
	chose to continue the job.
System Action:	Processing continues to the execution phase.
User Response:	None.

# SD422-XXX WARNING ERRORS HAVE BEEN FOUND 0-OK, CONTINUE 2-NOT EXPECTED, CANCEL

Code: Explanation:	A—Action No severe or terminal errors were found in the data supplied in your sequence
	specification statements. However, warn- ing errors were found.
System Action:	Halt C123 (Model 6) or halt 22 (Model 10, Model 12, or Model 15) occurs.
User Response:	The operator should review the warning errors on the listing to decide what action to take, and then respond to the halt with option 0 (OK—continue the job) or option 2 (errors not expected—cancel the job).

# SD423-PERMANENT I/O ERROR READING SPECIFICATIONS

Code:	A–Action
Explanation:	A permanent I/O error has occured dur-
	ing the reading of your sort sequence
	specifications statements.
System Action:	This disk sort job cannot continue. Halt
	CD3 (Model 6) or halt 23 (Model 10,
	Model 12, or Model 15) occurs.
User Response:	Option 3–Immediately cancel this job.
	Resubmit job. If error persists, contact
	IBM for hardware support.

### SD425-SEVERE AND/OR TERMINAL ERRORS FOUND

Code:	A–Action
Explanation:	Severe and/or terminal errors were found during the generation phase of disk sort.
System Action:	This job cannot continue. Halt CD45 (Model 6) or halt 25 (Model 10, Model 12, or Model 15) occurs.
User Response:	Option 3–Immediately cancel this job.

### SD450-XX,XXX MAIN STORAGE BYTES ASSIGNED

Code:	I-Information
Explanation:	This is the size of main storage in which disk sort has been assigned to run.
System Action:	None.
User Response:	None.

# SD451-XXXX BYTES-INPUT FILE RECORD LENGTH

Code:	I-Information
Explanation:	This is the input record length.
System Action:	None.
User Response:	None.

#### SD452-XXXX BYTES-WORK FILE RECORD LENGTH

Code:	I-Information
Explanation:	This is the record length for your work
	file. It was computed from the informa-
	tion on your header line.
System Action:	None.
User Response:	None.

# SD453-XXXX BYTES-OUTPUT FILE RECORD LENGTH

Code:	I-Information
Explanation:	This is the record length for your output
	file. This information is taken from your
	header line.
System Action:	None.
User Response:	None.

# SD454-XXXX BYTES-INPUT FILE BLOCK LENGTH

Code: Explanation:	I—Information This is the block length for your input file. This information is taken from your
System Action: User Response:	input FILE statement. None. None.

## SD455-XXXX BYTES-OUTPUT FILE BLOCK LENGTH

Code:	I-Information
Explanation:	This is the block length for your output file. This information is taken from your output FILE statement.
System Action: User Response:	None.

## SD461-XXXX BYTES-SELECT/BUILD ROUTINE

Code:	I-Information
Explanation:	The sequence specifications for this job (including alternate collating statements, if specified) will use the specified number
	of bytes of main storage.
System Action:	None.
User Response:	None.

# SD462-XXX SEQUENCE SPECIFICATION STATEMENTS PROCESSED

Code:	I-Information
Explanation:	This is the number of sequence specifica-
	tions statements (processed by the genera-
	tion phase) in your job.
System Action:	None.
User Response:	None.

SD500-5445 FEATURE NOT AVAILABL	E (Model 10
only)	

Code:	T—Terminal
Explanation:	An attempt has been made to use a 5445
	disk; however, the IBM System/3 Disk
	Sort 5445 Disk Storage Drive Feature is
	not on the program pack.
System Action:	The job ends.
User Response:	Either specify another device type or per-
	form system generation with Disk Sort
	5445 support.

SD501-DISK SORT TAPE SUPPORT NOT AVAILABLE (Model 10 only)

T–Terminal
An attempt has been made to use tape
input or output; however, IBM System/3
disk sort tape support is not on the pro-
gram pack.
The job ends.
Either specify another device type or per-
form system generation with disk sort
tape support.

# SD600-XX-FIRST PASS-#0 PASS-STARTED

Code: Explanation:	I–Information The execution phase of your job has
Explanation	begun. Records are being copied from
	the input file to the work file (XX =
	execution phase).
System Action:	None.
User Response:	None.

#### SD601-#XX PASS COMPLETED

NNN

Code:	I-Information
Explanation:	This is simply status information. It tells you that pass #XX has just been success- fully completed. (The first pass #00, the second pass is #01, etc.) NNN is design information for the Model 15 (5704-SM9). For further explanation, see the diagnostic aids in the <i>IBM System/3 Disk Sort Program</i> <i>Logic Manual</i> , LY21-0517.
System Action:	None.
	None.
User Response:	NULLE.

# SD602-XXXXXX INPUT RECORDS WERE READ IN

Code:	I-Information
Explanation:	Number of records read from the input
	file.
System Action:	None.
User Response:	None.

# SD603-NNNNNN RECORDS WERE SELECTED TO BE SORTED

Code:	I–Information
Explanation:	How many of the records just read in are
	going to be sorted.
System Action:	None.
User Response:	None.

## SD605-CCP DATA TRUNCATED

Code:	I–Information
Explanation:	More than 80 bytes of data were passed or entered for the chain request. Only the
	leftmost 80 bytes of data were retained,
	the remainder was truncated.
System Action:	None.
User Response:	Review your task chain request to deter- mine the impact of the truncation.

# SD62C-NO INPUT RECORDS WERE SELECTED TO BE SORTED

Code:	A–Action
Explanation:	Of the number of input records specified
	in message SD602, none of them met the
	INCLUDE requirements of your sort
	sequence specifications.
System Action:	Halt C1234 (Model 6) or halt 2C (Model 10,
	Model 12, or Model 15) occurs.
User Response:	Take option 0 to continue the job and
	create a null output file or take option 3
	(immediate cancel). Review your sequence
	specifications in light of the records actual-
	ly in your input file.

## SD681-WORK RECORD COUNT IN ERROR

Code:	T–Terminal
Explanation:	Disk sort internal error.
System Action:	The job terminates.
User Response:	Collect pertinent information and contact
	IBM for programming support.

#### SD690-DISK SORT STARTING FINAL PASS

Code:	I-Information			
Explanation:	The final pass of this sort job has begun.			
	Records are being written on your output			
	file.			
System Action:	None.			
User Response:	None.			

#### SD900-TASK CHAIN UNSUCCESSFUL

Code: Explanation:	I—Information The task chain request could not be completed.
System Action:	None.
User Response:	Ensure that your task chain request is correct, and determine the impact of an unsuccessful chain on your job stream.

### SD691-FINAL PASS SUCCESSFULLY COMPLETED

Code:	I—Information			
Explanation:	The last pass of this sort was just success-			
	fully completed.			
System Action:	None.			
User Response:	None.			

# SD692-XXXXXX SORTED RECORDS PLACED ON OUTPUT FILE

Code: Explanation:

System Action:

User Response:

I-Information The last pass of this sort was just successfully completed. The output record selected and generated from the input records have been sorted and placed on your output file. None. None.

#### SD693-NO INPUT RECORDS FOUND

Code:A-ActionExplanation:No records were found in the input file.System Action:Halt C1234 (Model 6) or halt 2C (Model<br/>10, Model 12, or Model 15) occurs.User Response:Check input file to ensure that it is the<br/>proper file and contains records you want<br/>to sort. Take option 0 to continue the<br/>job and create a null output file or take<br/>option 3 (immediate cancel).

#### SD694-XX PASSES REMAINING

Code:	I–Information
Explanation:	This is the number of passes remaining until
	job completion. NNN is design information
	for the Model 12 and Model 15. For further
	explanation, refer to the diagnostic aids in
	the IBM System/3 Disk Sort Program Logic
	Manual, LY21-0517.
System Action:	None.
User Response:	None.

#### SD695-XXXX USED FOR WORK FILE

Code:	I–Information					
Explanation:	This is the number of tracks of work file used in this sort.					
System Action:	None.					
User Response:	None.					

NNN

### SD711-MOUNT OUTPUT TAPE

Code:A--ActionExplanation:The output tape is not required until the<br/>intermediate merge passes are done.System Action:The program halts.User Response:Mount the tape. If the output file uses<br/>the same tape drive as the input file, re-<br/>move the input file and replace it with<br/>the output file reel. Do not reply to the

halt until the output file reel is mounted.

#### SD929-WORK FILE PERMANENT I/O ERROR

Code:	A–Action
Explanation:	A permanent unrecoverable I/O error has occurred during the reading of records from your work file.
System Action:	The job cannot continue. Halt CD4 (Model 6) or halt 29 (Model 10, Model 12, or Model 15) occurs.
User Response:	Option 3 (immediate cancel). Resubmit the job. If error persists, contact IBM for hardware support.

### SD92A-OUTPUT FILE PERMANENT I/O ERROR

Code:	A–Action
Explanation:	A permanent unrecoverable I/O error has occurred writing to your output file.
System Action:	The job cannot continue. Halt CD34 (Model 6) or halt 2A (Model 10, Model
	12, or Model 15) occurs.
User Response:	Option 3 (immediate cancel) or option 2 (controlled cancel). Resubmit the job. If error persists, contact IBM for hardware support.

### SD92D-SORT TASK CHAIN ATTEMPT FAILED

rs,	Code:	A–Action
	Explanation:	After executing a CCP/Disk Sort
		program, the attempt to chain to the next
		task was not successful. Either not
		enough task chain queues were specified
		in the assignment set, or there is
		insufficient TP buffer space.
has	System Action:	Message 2D (Model 15, 5704-SM7 only)
ds	User Response:	Option 1 (retry). Attempt to execute
		the task chain again. Option 2
		(controlled cancel). The next program
		must be initiated by the operator.

#### SD901-\*\*\*\*\*NORMAL EOJ\*\*\*\*\*

Code:	I-Information
Explanation:	The sort job has been completed.
System Action:	None.
User Response:	None.

#### SD902-\*\*\*\*\*ABNORMAL EOJ\*\*\*\*\*

Code:	I-Information
Explanation:	Errors have prevented the sort job from
	being run.
System Action:	None.
User Response:	Review previous messages, correct errors,
	and resubmit job.

#### SD928-INPUT FILE PERMANENT I/O ERROR

Code:	A–Action
Explanation:	A permanent, unrecoverable I/O error has
	occurred during the reading in of records
	from your input file.
System Action:	The job cannot continue. Halt C125
	(Model 6) or halt 28 (Model 10, Model
	12, or Model 15) occurs.
User Response:	Option 3 (immediate cancel). Resubmit
	the job. If error persists, contact IBM for
	hardware support.

# SD92E-WORK FILE TOO SMALL

Code:	A–Action	Code:	A
Explanation:	While building the work file, disk sort ran out of space.	Explanation:	Whe nee
System Action:	The job cannot continue. Halt C1245 (Model 6) or halt 2E (Model 10, Model 12, or Model 15) occurs.		fou or v sort
User Response:	Option 3 (immediate cancel). Allocate more tracks for the work file, and resub-	System Action:	Hal Mod
	mit the job. If automatic work file allocation is being used, you can make more work area available by deleting un- necessary files (preferably on the fixed	User Response:	Opt occi the occi
	units), or by mounting a pack having ade- quate work area available. If automatic work file allocation is not being used, you		allo to b
	can make more work area available by us- ing a file statement designating adequate work area.		cano a di or n
			mit

# SD92F-OUTPUT FILE TOO SMALL

ode:	A–Action
planation:	When calculating the number of tracks
	needed for the output file, disk sort
	found that the output file was too small,
	or while writing to the output file, disk
	sort ran out of space.
stem Action:	Halt CD2 (Model 6) or halt 2F (Model 10,
	Model 12, or Model 15) occurs.
er Response:	Option 1 (controlled cancel). If the halt
	occurs prior to the intermediate passes of
	the sort, another halt will be likely to
	occur in the later phases. A 1-option will
	allow the sort to take place and records
	to be put on the output file until no more
	space is available. Option 3 (immediate
	cancel). Either allocate more tracks for
	a disk output file or use a larger tape reel
	or multireel for a tape output file. Resub-
	mit the job.

# Appendix G. Instructions for Executing the Disk Sort Sample Program

When you receive the disk sort program, perform the following installation procedures:

- 1. If you received the disk sort program with the system control programs and have performed the program product generation during system generation, go to step 3.
- 2. For your system, perform the operations for Program Product Generation and Completing System Generation described in the *Operator's Guide*
- 3. You should now verify that the disk sort program is operational by executing the disk sort sample program. General operating procedures for disk sort may be found in the Operator's Guide. To execute the sample program, perform the procedure under Sample Program; to execute it on the Model 6, perform the procedure under Sample Program for Model 6.

Note: There is no sample program for CCP/Disk Sort.

#### Sample Program for Model 6

For the Model 6, the disk sort sample program is a procedure on the distribution disk cartridge.

Mount distribution disk cartridge on R1 and set the DISK DRIVE 1 ON/OFF SWITCH to ON. When the disk drive is ready for use, move PROGRAM LOAD switch to ON.

You must now respond to the keywords that appear on the data entry keyboard.

Keyword		Your Keyboard Response
DATE		mmddyy (current month, date, and year) and press PROG START.
READER-		Press PROG START.
READY-	е — <u>н</u>	LOAD and press PROG START.
LOAD	NAME-	\$D\$SPL and press PROG START.
	UNIT-	R1 and press PROG START.
DATE	(mm/dd/yy)—	Press PROG START.
SWITCH	(0000000)—	Press PROG START.
FILE	NAME-	INPUT and press PROG START.
	UNIT-	R1 and press PROG START.
	PACK-	Enter the proper pack identification and press PROG START.
	LABEL-	Press PROG START.
	RECORDS-	Press PROG START.
	TRACKS-	1 and press PROG START.
	LOCATION-	Press PROG START.
	RETAIN-	T and press PROG START.
	DATE-	Press PROG START.

Keyword		Your Keyboard Response
FILE	NAME-	Press PROG START.
MODIFY		RUN and press PROG START. \$G RECL-0096, REC#-000064 and press PROG START.
READY-		CALL and press PROG START.
CALL	NAME-	\$D\$SP1 and press PROG START.
	UNIT-	R1 and press PROG START.

These are all the responses that you must make. When the sorted file is printed, the records should be in descending order in columns 10-15. When the READY keyword appears, the sample program has ended.

Sample Program for Model 8, Model 10, Model 12, and Model 15

For the Model 8, Model 10, Model 12, and Model 15, the disk sort sample program is a procedure on the distribution disk cartridge.

With the system on F1, mount distribution disk cartridge on R1 and set the DISK DRIVE 1 ON/OFF SWITCH to ON. The READY light indicates when the disk drive is ready for use. If the system input device is other than the MFCU, set the ADDRESS/DATA switches as required. Set the PROGRAM LOAD SELECTOR to REMOVABLE DISK. Press PROGRAM LOAD, and enter the following statements via your system input device.

// DATE mmddyy // LOAD \$D\$SPL, R1 // FILE NAME-INPUT, UNIT-R1, PACK-XXXXXX, TRACKS-1 // RUN \$G RECL-0096, REC #-000064 /& // CALL \$D\$SP1, R1 // RUN

where mmddyy = correct date. XXXXXX = proper pack identification.

These are all the entries that you need to make. As the sorted file is printed, the records should be in columns 10-15. The READY light indicates that the sample program has ended.

For the Model 8 or Model 10, EJ is displayed when the file to be sorted has been built. To continue with the sort job, press console START or, if you have DPF, the program 1 HALT/RESET key.

#### Appendix H. CCP/Disk Sort Specifications Differences

This appendix is designed as a reference guide for the following System/3 CCP/Disk Sort users:

- Model 4, Program Number 5703-SM2
- Model 15, Program Number 5704-SM7

#### **CCP/DISK SORT OVERVIEW**

The IBM System/3 CCP/Disk Sort Program is a disk-resident program which sorts a data file into either ascending or descending sequence. The sorting is executed under the control of the Communications Control Program (CCP) on System/3 Models 4 or 15. Any disk file organization supported by the System/3 disk system management may be used as input to the sort. This includes indexed, direct, and sequential files.

The user supplies OCL statements and sort specifications to the CCP/Disk Sort generator program (\$DGSRT). \$DGSRT does not run under control of CCP; rather, it generates an object program that can later be executed as a user task under CCP control. This same object program can also execute in a batch mode, rather than under CCP. In order to execute the object program, either in batch mode or under CCP, the entire CCP/Disk Sort Program (\$DG.ALL) must be present on the program pack during execution.

The CCP/Disk Sort Program requires the use of the Overlay Linkage Editor during the generation phase. The Overlay Linkage Editor must reside on the same pack on which the CCP/Disk Sort Program resides.

OCL statements for \$DGSRT can be supplied from the system input device or from a procedure library member. Sort specifications can be supplied from the system input device, from a procedure, or from a source library member.

A listing of the sort specifications and informational messages is optional. (See column 27 in Chapter 3.) When requested, they are listed on the printer only if log on is specified.

### FILE STATEMENT CONSIDERATIONS

For CCP/Disk Sort generation, the FILE statements for input, work, and output are needed to provide the LABEL parameters. The LABEL parameters are used as the file NAME for the object program execution. This is done so that multiple sorts can be executed in a single CCP session.

If any of the sort files (input, work, and output) are physically online during generation, the FILE statement must be valid for that file.

If the sort file is not online the FILE statement must still be syntactically correct and contain a TRACKS parameter and a valid LABEL parameter. The UNIT and TRACKS parameters do not have to be the actual values to be used when running the sort, but they must be present. The UNIT parameter cannot specify a nonremovable unit.

**\$SOURCE** and **\$WORK** files must be provided for the generation of the object module, and both files must reside on a 5444 simulation area.

#### Multiple Input Files (Model 15 only)

Input can be from either of the following devices:

- 3340 Direct Access Storage Facility
- 3344 Direct Access Storage

Up to eight files can be used as input using any combination of the preceding devices. The file names for generation must be INPUT or INPUT1 (but not both), INPUT2, INPUT3, INPUT4, INPUT5, INPUT6, INPUT7, and/or INPUT8<sup>1</sup>.

The files are processed INPUT (or INPUT1) serially to INPUT8 regardless of the order of the OCL FILE statements. The lowest numbered input file is processed fully first, then the next numbered input file will be processed in its entirety, then the next until all the files have been individually processed in sequence. For a particular disk sort run, the input files do not have to be numbered serially; that is, the file names may be INPUT3, INPUT5, and INPUT8<sup>1</sup>, or a particular run could have just INPUT8 as the input file.

*Note:* The record lengths of all disk files must be the same. Also note that the UNIT parameter *is* used.

<sup>1</sup> The LABEL parameters are used as the file NAME for the object program execution.

**Output File Over Input File Considerations for Model 4** 


If Input File Is	Output Over Input?
Direct <sup>1</sup>	No
Indexed <sup>1</sup>	No
Sequential	Yes
<sup>1</sup> Addrout sort is recomm	nended.

#### Work Record Length

Work record lengths cannot be less than three bytes. This means that the length of the sort control field, plus the length of the data fields (if any), must be three bytes or greater. If the work record length is less than three bytes, a diagnostic message (SD391) will be issued during sort generation and the sort cannot be executed. If necessary, specify a minimum 3-byte control field which you can drop (X in column 28 of the header statement) at output time. Be careful, there may be data in portions of the control field that may be required in the output record.

*Note:* The work record length discussed is not the value specified in the CCP DISKFILE statement. The record length specified in the DISKFILE statement for the work file must always be 256.

# CCP/Disk Sort Object Program Generation Job Stream Example




The overlay linkage editor requires that the \$SOURCE and \$WORK files be 10 tracks.

5 The LABEL keyword identifies the actual input file name at execution time (infile – see item of CCP Assignment Set Statement Example).

6 Same as for Disk Sort (see the discussion on OCL. Statements in Chapter 2). Also see the heading File Statement Considerations in this appendix.

7 The FILE statement for WORK must be present in CCP/Disk Sort.



9 The LABEL keyword identifies the actual output file name (outfil – see item 3 of CCP Assignment Set Statement Example).

**10** The header specification field definitions for columns 1-34 for CCP/Disk Sort are the same as those defined for disk sort (see Chapter 3).

CCP/Disk Sort header specification field definition variations for columns 35-80 follows.

*Note:* The last page of this appendix contains a CCP/Disk Sort Sequence Specification form. This form is provided for your use and you may make copies from it. It cannot be ordered through your IBM representative.

Users who have other system installations can still use the standard sequence specifications form (GX21-9089) or equivalent. Be aware that the changes in the header specification start with column 37 for CCP/Disk Sort.

*Columns 35-36* are reversed for system use. Column 35 cannot be used because only one sort algorithm exists.

*Columns 37-38* contain the Model 15 storage size required to execute the object module. Specify a value from 12K to 48K in 2K increments.

*Column 39:* Model 4 must contain an R, which indicates that a record length exists in columns 40-43. Model 15 must contain either a C or an R. A C indicates that the sort chains to the next task. An R or C indicates that a record length exists in columns 40-43.

*Note:* For program numbers 5799-ATF, 5799-ATG, and 5799-ATH, column 39 can contain only an R.

*Columns 40-43* contain the input file record length, right justified with or without leading zeros.

*Note:* If a user comment exists in columns 40-43, you must either shorten the comment or remove it.

*Columns* 44-72 contain any comment you wish to use.

*Note:* If you are redoing the header statement for a program not previously used by CCP/Disk Sort, remember to rewrite the comment since columns 40-43 now contain data of a different nature.

#### Columns 73-74 are not used.

*Columns 75-80* contain the name given to the object program. This is the name that you enter from the terminal to invoke the sort. The entry can be:


- A valid program name. The first character must be alphabetic, but cannot be a #, \$, or @ character. The remaining characters must be alphameric with no embedded blanks or special characters.
- 2. Blank. The default is SRTOBJ.

*Note:* DIR, ALL, and SYSTEM are reserved names and must not be used as program names.

**11** For record type specifications, see Chapter 4.

For field specifications, see Chapter 5.

#### **CCP** Assignment Set Statements Example



SAMPIN (infile) is the same LABEL keyword given for FILE NAME-INPUT in the job stream (see item in the Sample CCP/Disk Sort Job Stream). This file can be SHR or NOSHR and the value of aaaa is the same value used in columns 40-43 of the header statement (record length).

SAMPWK (wrkfil) is the same LABEL keyword given for FILE NAME-WORK in the job stream (see item in the Sample CCP/Disk Sort Job Stream). This file must be NOSHR and RECL must be 256.

SAMPOT (outfil) is the same LABEL keyword given for FILE NAME-OUTPUT in the job stream (see item **7** in the *Sample CCP/Disk Sort Job Stream*). This file must be NOSHR. The value of bbb can be:


The value specified in columns 29-32 of the header statement.

• A 3 if SORTA is specified.

2

3

CCP/Disk Sort Execution (Batch Mode) Job Stream Example



The name is the name given to the object program in columns 75-80 of the header card at generation time. If no name was specified, the default is SRTOBJ.

1

2 These parameters must all be correct for the input, work, and output files.

Appendix I points out the differences between the CCP/Disk Sort Programs for Models 8, 10, 12, and 15A, 15B, and 15C and the corresponding Disk Sort Program for these systems. For a description of the CCP/Disk Sort Program, refer to Appendix H of this manual.

These CCP/Disk Sort Programs are classified as programming RPQs (request for price quotation) rather than as Program Products. Your IBM marketing representative can provide information about RPQs.

*Note:* Automatic work file allocation is not supported by CCP/Disk Sort Programs.

# CCP/DISK SORT PROGRAM (PROGRAM NUMBER 5799-ATF)

This CCP/Disk Sort Program is used on System/3 Model 8 or 10, and operates under control of SCP 5702-SC1. The generated object program can be executed under control of the Communications Control Program (program number 5702-SC1, feature 6033). The CCP/Disk Sort Program (program number 5799-ATF) is functionally identical to the Disk Sort Program for the Models 8 and 10 (Program Product number 5702-SM1).

Using CCP/Disk Sort, sort generation requires 12K bytes of main storage and a 5444 Disk Storage Drive.

To execute the generated sort program, 12K bytes of main storage is required. The following devices are supported for the input, work, and output files:

- 5444 Disk Storage Drive
- 5445 Disk Storage
- 5448 Disk Storage Drive

# CCP/DISK SORT PROGRAM (PROGRAM NUMBER 5799-ATG)

This CCP/Disk Sort Program is used on System/3 Model 12 and operates under control of SCP 5705-SC1. The generated object program can be executed under control of the Communications Control Program (program number 5705-SC1, feature 6070 or 6071). The CCP/Disk Sort Program is functionally identical to the Disk Sort Program for the Model 12 (Program Product number 5705-SM1) with one exception, only one input file can be specified on this CCP/Disk Sort Program.

Using CCP/Disk Sort, sort generation requires 12K bytes of main storage and a 3340 Direct Access Storage Facility.

To execute the generated sort program, 12K bytes of main storage is required. Input, work, and output files can reside in the main data area or in the simulation area of a 3340 Direct Access Storage Facility.

# CCP/DISK SORT PROGRAM (PROGRAM NUMBER 5799-ATH)

This CCP/Disk Sort Program is used on System/3 Model 15A, 15B, or 15C and operates under control of SCP 5704-SC1. The generated object program can be executed under control of the Communications Control Program (program number 5704-SC1, feature 6033, 6070, or 6071). The CCP/Disk Sort Program is functionally identical to the Disk Sort Program for the Model 15 (Program Product number 5704-SM1) with one exception, the only devices supported by the CCP/Disk Sort Program for the input, work, and output files are the following:

- 5444 Disk Storage Drive
- 5445 Disk Storage
- 3340 Direct Access Storage Facility

In using CCP/Disk Sort, sort generation requires 12K bytes of main storage.

To execute the generated sort program, from 12K to 48K bytes can be specified; however, the maximum task size under CCP is 32K bytes.

**ADDROUT sort:** The type of sort where the output consists of record addresses in the input file.

alphabetic character: Letters A through Z and special symbols #, \$, and @.

alphameric character: The alphabetic characters defined and numeric characters 0-9.

**block:** A predefined unit of storage space for files on the disk. For example, 1 block = 2560 bytes.

**byte:** The representation of a character by eight binary digits; the amount of storage required for one EBCDIC character.

**conditional force:** The control field character is replaced before the record is sorted, only if the control field in the input record contains a particular entry.

**constant:** Data that does not change during execution of a program.

control field: One or more specified fields that are compared to determine the record sequence in the output file.

data: A collection of facts, numbers, letters, and symbols that can be processed by a computer.

data field: See field.

**execution phase:** The part of the sort program that gets the records you want to sort, sorts the records, and writes the sorted records onto the output file.

**field:** One or more adjacent record positions that contain related information.

file: An organized collection of related records.

**file description:** The specification for the arrangement of fields within a record and records within a file.

**forced control field:** A one-position control field that results from replacing the value or adding a value.

generation phase: The part of the sort program that translates the sequence specifications into machine language.

input: Data transferred to computer storage for processing.

integer: A whole number stored in hexadecimal (binary) form.

**library:** An area on disk that contains procedure members, source members, load members, and subroutine members as well as areas required by the system control program. For example, sort is stored in the library.

normal control field: Any control field that is specified by an N in column 7 of the field sequence specifications.

OCL: Operation control language.

**OCL statement:** A statement that identifies the job and its processing requirements to the control program.

**opposite control field:** Any control field that is specified by an O in column 7 of the field sequence specifications.

output: Data transferred from computer storage to printed form, disk, or to the display screen.

output file: File resulting from the sort.

overflow field: In a summary tagalong sort, the field that allows for anticipated field expansion.

**packed data field:** Each byte within a field represents two numeric digits except the low-order byte, which contains the sign. For non low-order bytes, bits 0-3 for one digit; bits 4-7 for one digit.

**procedure:** A named collection of related OCL statements, and possibly control statements that perform a particular task.

procedure member: A procedure stored in the library.

**program date:** The date associated with a program (job step).

real number: A number stored in IBM System/360 floating-point format, in which the leftmost byte contains the sign and exponent (decimal location) and the remaining bytes contain the fraction or mantissa in left-justified binary form.

**record:** A collection of related data, treated as a unit. For example, one line of an invoice might form a record.

relative record number: In a direct file, the location of a record in relation to the beginning of the file.

**right-justify:** The placement of data in a field with the last significant byte in the rightmost position.

sequence specification. Defines the arrangement of a file.

source member: A collection of records used as input to a program such as RPG II specifications or sort sequence specifications. Source members are stored in the library.

summary data field: In a summary tagalong sort, a data field designated for accumulated totals.

summary tagalong sort: A type of sort that arranges records by a specified control field and accumulates totals from specified fields within those records.

tagalong sort: A type of sort that arranges records by a specified control field and includes other specified data fields in the output.

**unpacked data field:** Each byte within a field represents one numeric digit. Bits 0 through 3 are reserved for the sign; bits 4 through 7 are the numeric portion.

work file: An area reserved on the disk for temporary storage of the data being sorted.

# Index

to indicate comments on field description line 37 to indicate comments on record type lines 30 // SOURCE statement in BUILD cycle for Model 6 98 in CALL cycle for Model 6 99 in LOAD cycle for Model 6 94 to supply sequence specifications for Model 10 and Model 15 92 //SWITCH statement, directed automatic work file allocation 14

action message (A) explanation of 121 printed by the disk sort program 24 address out sort (addrout), definition and function 5 addrout and tag along sorts, comparison of 14 addrout sort (SORTA) (see SORTA) alphameric constants, as factor 2 (columns 20-39-record type specifications) 35 alphameric data as affected by column 8 record type entry 30 effect on column 8 record type entry 31 alternate collating sequence ALTSEQ statement use 107 effect on factor 1 and factor 2 comparison 34 effect on sort time 111 indicated on header line (column 26) 23 restrictions on using column 8 record type entries 107 ALTSEQ statements examples of 108 how to code 107 placement in sequence specifications 108 programming considerations 108 what they can and cannot change 108 AND lines definition 29 describing a record type 28 describing additional factor 1 fields 34 in include sets 28 in omit sets 29 ASCII file 10, 11, 12 automatic work file allocation directed 5445, Models 12 and 15 13, 14 effect on sort time 113 file considerations 13, 14 multiple file input 10, 11, 12

binary relative record number 5 BUILD cycle for Model 6 function 91 keyword-response summaries 95 when to use 91 bytes in a track, number of 3340, for the 116 5444, for the 116 5445, for the 116

C/Z/D/P/U (column 8-record type specifications) effect on factor 1 length (columns 9-16) 34 restrictions when using alternate collating sequence 31 to indicate packed or unpacked data 30 to indicate portions of characters to compare 31 to indicate records you want to sort 31 when factor 1 and factor 2 contain alphameric data 31 with signed and unsigned data 31 C/Z/D/P/U/V (column 8-field description specifications) effect on your sorted file 40 what it tells disk sort 40 calculating file size 116 CALL cycle for Model 6 function 91 keyword-response summaries 99 when to use 91 CCP/disk sort \$SOURCE 150 **\$WORK 150** field description specifications (see field description specifications) FILE statement considerations 150 header specifications column summary 22 column 6 (line type) 23 column 18 (sequence) 23 column 26 (collating sequence) 23 column 27 (print option) 24 column 28 (output option for SORTR) 24 column 34 (nonverify option) 24 columns 37-38 (storage size) 25, 151 column 39 (record length code) 25, 151 columns that you must fill in 22, 151 columns 1-2 (page numbers) 23 columns 3-5 (line number) 23 columns 7-12 (job) 23 columns 13-17 (largest total of control fields of any record type) 23 columns 29-32 (output record length for SORTR) 24 columns 40-43 (record length) 25, 151 columns 44-72 (iob description) 25, 151 columns 75-80 (program name) 25, 151

CCP/disk sort (continued) overview 148 record type specifications (see record type specifications) sample CCP assignment set statements 152 sample job stream 150 specifications, differences in 150 work record length, specifying 150 characters in compare operations 30 representation within the computer 31 collating sequence (column 26-header specifications) alternate 107 specified for compare operations 23 standard 107 table of 106 column 5 (field description specifications), to add new sequence lines without renumbering 37 column 5 (record type specifications), to add new sequence lines without renumbering 26 column 6 (line type) field description specifications 37 header specifications 22 record type specifications 26 column 7 (continuation or comments), record type specifications 30 column 7 (field type or comments), field description specifications 38 column 8 (C/Z/D/P/U) record type specifications 30 column 8 (C/Z/D/P/U/V) field description specifications 41 column 17 (conditionally forced character), field description specifications 45 column 18 field description specifications (forced character) 45 header specifications (sequence) 22 column 19 field descriptions (specifying replacements) 46 record type specifications (field or constant) 34 column 26 (collating sequence), header specifications 22 column 27 (print option), header specifications 22 column 28 (output option), header specifications 22 column 34 (nonverify option), header specifications 22 column 39 (CCP/disk sort record length code), header specifications 25, 151 columns 1-2 (page number) field description specifications 37 header specifications 22 record type specifications 26 columns 3-5 (line number) field description specifications 37 header specifications 22 record type specifications 26 columns 7-8 (field description specifications), possible combinations of entries 37, 43 columns 7-12 (job), header specifications 22 columns 9-12 (from entry), field description specifications 37, 44 columns 9-16 (factor 1 location), record type specifications 26, 34 columns 13-16 (to entry), field description specifications 37, 44 columns 13-17 (largest total of control fields of any record type), header specifications 22

columns 17-18 (relation), record type specifications 26, 34 columns 20-22 (overflow field length entry), field description specifications 37, 52 columns 20-27 (factor 2 field), record type specifications 26, 35 columns 20-39 (factor 2 constant), record type specifications 26, 35 columns 29-32 (output record length), header specifications 22, 24 columns 40-43 (CCP/disk sort record length), header specifications 25, 138 columns 40-72 (comments) field description specifications 37, 52 record type specifications 26, 36 columns 40-72 (job description-disk sort), header specifications 22, 25 columns 44-72 (CCP/disk sort job description), header specifications 25, 151 columns 75-80 (program identification/program level), header specifications CCP/disk sort 25, 151 disk sort 25 comment line field description specification 38 record type specifications 30 comments (columns 40-72-field description specifications) 37, 52 comments (columns 40-72-record type specifications), to describe record types 26, 36 compare operations affected by column 8 of record type specifications 30 affected by column 19 of record type specifications 35 affected by columns 17-18 of record type specifications 34 conditional force explanation of 39 using a force-all line 51 using normal or opposite and forced control fields 49 using only forced control fields 48 conditionally forced character (column 17-field description specifications) examples 48 how to define 46 used to assign value to summary overflow field 46 what it tells disk sort 45 constant as factor 2 (columns 20-39-record type) 35 indicated by column 19 of record type specifications 35 length when used as factor 2 on record type specifications 35 position when used as factor 2 on record type specifications 35 positioning sign in numeric constants 35 continuation or comment (column 7-record type specifications) to describe different record types having identical field types 30 to further describe the same record type 30 to indicate comment line 30 to indicate start of include or omit set 30 control and data fields, when and how to describe one field as both 24

control fields forced 39 how order affects sort time 113 how to drop 24 normal 39 number of when two or more record types 38 opposite 39 packed or unpacked 41 specifying use by disk sort 38 to sequence information in sorted records 42 total lengths when two or more record types 38 types of 39 when to drop 41 conversational OCL for Model 6 interrelationship with sequence specifications 101 summary of keywords and responses for OCL cycles 92 to supply OCL statements 9, 16 when to use each OCL cycle 91 cycles, OCL functions of 91 list of 91

data alphameric 31 numeric 32 representation within the computer 31 used in compare operations 30 data and control fields, when and how to describe one field as both 24 data fields definition 38 describing on field description line 38 number of when two or more record types 38 total lengths when two or more record types 38 data fields, summary (see summary data fields) data recorder, to supply OCL statements 16 defining conditional force characters 46 force-all characters 46 unconditional force characters 46 diagnostic messages print option 24 digit portion of System/3 character 31 disk address 5 disk sort program execution phase 121 files used 6 general description 3 generation phase 121 information OCL statements give your computer 9 input needed 6 interaction with input, work, and output files 4 timings, sample 106 dropping control fields how to do it 22, 24 when to do it 41

error messages explanation of codes 121 list of 122 example of using force 63 examples of addrout and tag along sorts 55, 72 examples of integer and real number sorting 83 examples of summary sort jobs 67 examples of using forced control fields 47 execution phase 121 external indicators 14

factor 1 (columns 9-16-record type specifications) changed by ALTSEQ statements 108 coding rules 34 coding when only one character 34 describing more than one factor 1 field 34 how length affected by column 8 entry 34 possible lengths 34 to identify included or omitted records 34 factor 2 (columns 20-27 or 20-39-record type specifications) changed by ALTSEQ statements 108 coding the sign in packed and unpacked numeric constants 35 how to position the numeric constant in columns 20-39 35 length of factor 2 constant 35 length of factor 2 field 35 rules for coding 35 factor 2 field (columns 20-27-record type specifications) coding rules 35 coding when one character long 35 relationship to factor 1 field 35 field description specifications (disk sort and CCP/disk sort) as part of include set 28 column summary 37 column 6 (line type) 38 column 7 (field type or comments) 38 column 8 (C/Z/D/P/U/V) 40 column 17 (conditionally forced character) 45 column 18 (forced character) 45 column 19 (specifying replacements) 46 columns you must fill in 37 columns 1-2 (page number) 38 columns 3-5 (line number) 38 columns 9-12 (from) 44 columns 9-16 (field location) 44 columns 13-16 (to) 44 columns 20-22 (overflow field length entry) 52 columns 40-72 (comments) 52 explanation of the column entries 38 what they describe for addrout sorts 38 what they describe for summary sort 38 what they describe for tag along sorts 38 what they tell disk sort 37 when using an include-all line 27 field length, dependent on column 8 entry (field description specifications) 45

field location (columns 9-16-field description specifications) to identify location of field in input record 44 field or constant (column 19-record type specifications) to determine if factor 2 is constant or field 35 field type or comments (column 7-field description specifications) 38 file considerations 10 file location on disk, effect on sort time 111 FILE statement considerations 150 force-all explanation 39 result if not used 46 used after conditional force lines 40 force-all character examples of 51 how to define 46 force, example of 63 forced character (column 18-field description specifications) used to initialize summary overflow field 46 when and how character is forced 45 forced control fields examples 47 rules for using 42 types 39 when to use 39 format of records definition 8 effect on order of sequence specifications 8 from entry (columns 9-12-field description specifications) describing one character field 44 to indicate first position of field in input record 44 from entry (columns 9-12-record type specifications) to indicate first position of factor 1 in input record) 34 from entry (columns 20-23-record type specifications) to indicate first position of factor 2 field in input record 35

generation phase 110

header specifications, CCP/disk sort column summary 22 column 6 (line type) 23 column 18 (sequence) 23 column 26 (collating sequence) 23 column 27 (print option) 24 column 28 (output option for SORTR) 24 column 34 (nonverify option) 24 column 39 (record length code) 25, 151 columns that you must fill in 22, 151 columns 1-2 (page numbers) 23 columns 3-5 (line number) 23 columns 7-12 (job) 23 columns 13-17 (largest total of control fields of any record type) 23 columns 29-32 (output record length for SORTR) 24 columns 40-43 (record length) 25, 151 columns 44-72 (iob description) 25, 151 columns 75-80 (program name) 25, 151

header specifications, disk sort column summary 22 column 6 (line type) 23 column 18 (sequence) 23 column 26 (collating sequence) 23 column 27 (print option) 24 column 28 (output option for SORTR) 24 column 34 (nonverify option) 24 columns that you must fill in 22 columns 1-2 (page numbers) 23 columns 3-5 (line number) 23 columns 7-12 (job) 23 columns 13-17 (largest total of control fields of any record type) 23 columns 29-32 (output record length for SORTR) 24 columns 40-72 (job description) 25 explanation of column entries 23 what they tell disk sort 22

include line, to select records to sort 27 include set definition 28 mixing with omit sets 28 rules for using 28 when to use 28 include-all line implied 8 to sort records that have not been included or omitted 27 information message (I) 121 initializing an overflow field 52 input file calculating storage tracks for 116 considerations 9 considering overlay when programming 13 defined during BUILD cycle 84 defined during LOAD cycle 81 how its position on disk affects sort time 112 input sequence specifications, order when using ALTSEQ 108 input to disk sort, file types that you can sort 6 instructions for executing disk sort sample program for Model 6 146

for Model 10 147 for Model 15 147

sort), to supply comments 25, 151

job (columns 7-12—header), to specify the type of sort 23 job description (columns 40-72—header specification for disk sort), to supply comments 25 job description (columns 44-72—header specification for CCP/disk largest total of control fields of any record type (columns 13-17-header specification), calculating entry 23 lenath factor 1 of record type specifications 34 factor 2 constant (columns 20-39-record type specifications) 35 factor 2 field (columns 20-27-record type specifications) 35 maximum field length for columns 7-8 (field description specifications) 43 line number (columns 3-5) with page number (columns 1-2) for sequencing field description specifications 38 header specifications 23 record type specifications 27 line type (column 6) to identify field description line (field description specifications) 38 to identify header line (header specifications) 23 to identify include line (record type specifications) 27 to identify include-all line (record type specifications) 27 to identify omit line (record type specifications) 27 LOAD cycle for Model 6 function 91 keyword-response summary 92 when to use 91

main storage size, effect on sort time 110 main storage, amount used by sequence specifications 111 messages alphabetic codes 121 list 122 types printed by the disk sort program 24 MODIFY keyword response in BUILD cycle 98 response in CALL cycle 99 response in LOAD cycle 94 multiple input files (Model 15 only) 149 multiple input support 10

nine-track tape considerations 16 nonverify option (column 34—header specifications) 24 timing considerations 110 normal control field changed by ALTSEQ statements 108 definition 39 how disk sort uses 39 number of records effect on order of the sequence specifications 8 effect on sort time 110

number of sequence specifications, effect on sort time 111 numeric constants, coding negative constants 35 numeric data

data formats and column 8 entry combinations 31 defined by column 8 record type entry 32 definition of types 30 numeric data (continued) explanation of positive and negative (signed) numeric data 32 indicated by column 8 of record type specifications 31 packed numbers 32 unpacked numbers 32

OCL cycles for Model 6 functions 91 list 91 summary of keywords and responses 92 OCL statements interrelationship with sequence specifications 101 supplying for Model 6 16, 91 supplying for Model 10 16, 102 supplying for Models 12 and 15 17, 102 what they tell about disk sort 9 what they tell about the input file 9 what they tell about the output file 9 what they tell about the sequence specifications 9 what they tell about the work file 9 with conversational OCL 16 with online data recorder 16 without online data recorder 16 omit line to exclude records from your sort 27 when and how to use 27 omit set definition 28 mixing with include set 29 rules for using 28 types 29 when to use 29 opposite control field changed by ALTSEQ statements 108 column 8 field description entry when sorting different record types 41 definition 39 how disk sort uses 38 when to use 42 **OR** lines definition 29 describing different record types 28 in include sets 29 in omit sets 29 order of sequence specifications affected by number and format of records 8 normal order 8 out-of-sequence lines how to insert in field description specifications 38 how to insert in record type specifications 27 output addrout sort 5 OCL statements and error messages 16 summary tag along sort 6

tag along sort 5

output file calculating storage tracks for 116 considerations 14 defined by BUILD cycle 97 defined by LOAD cycle 93 how position on disk affects sort time 111 OCL statements needed if input file is temporary 9 overlaying input file (RETAIN-S vs RETAIN-T) 13 output option for SORTR (column 28-header specification) to drop control fields in tag along (SORTR) sorts 24 output record length for SORTR (columns 29-32-header specifications) calculating when dropping control fields 24 calculating when not dropping control fields 24 overflow field length entry (columns 20-22-field description specifications) 52 overflow indicator field how to define (columns 7-8-field description specifications) 46 how to initialize (column 18-field description specifications) 52 when to use 52 overview of disk sort 3

packed numeric data number of bits in each digit 32 position of sign code 32 possible positive and negative sign codes 32 packed, unpacked, opposite character, or opposite zone control fields 41 page number (columns 1-2) with line number (columns 3-5) for sequencing (see line number) print option (column 27-header specifications), information disk sort can print 24 programming considerations card input 97 data station input 97 moving a character 97 using disk sort 18

record length (columns 40-43—header specification for CCP/disk sort), to specify 25, 151 record length code (column 39—header specification for CCP/disk sort), to specify value 25, 151 record size

calculating for tag along (SORTR) sort 24 effect on sort time 110

record type specifications (disk sort and CCP/disk sort) column summary 26 column 6 (line type) 27 column 7 (continuation or comments) 30 column 8 (C/Z/D/P/U) 30 column 19 (field or constant) 35 columns you must fill in 26 columns 1-2 (page number) 27 record type specifications (disk sort and CCP/disk sort) (continued) columns 3-5 (line number) 27 columns 9-16 (factor 1 location) 34 columns 17-18 (relation) 34 columns 20-27 (factor 2 field) 35 columns 20-39 (factor 2 constant) 35 columns 40-72 (comments) 36 explanation of column entries 26 what they tell disk sort 26 when not required 26 record types described in include set 28 described in omit sets 29 records, how number of affects sort time 110 relation (columns 17-18-record type specifications) effect on omitting or including records 34 to specify factor 1 and factor 2 comparison 34 replacements for more than one character (column 19-field description specifications), when and how to indicate

sample disk-sort timings 114 sample jobs using addrout (SORTA) and tag along (SORTR) sorts 55 using signed control fields 72 using summary (SORTRS) sort 67 sample program instructions for executing on Model 6 146 instructions for executing on Models 8, 10, 12, and 15 147 sequence changing collating sequence of one character 108 changing collating sequence of several characters 108 standard and alternate collating 107 sequence (column 18-header specifications), to indicate record sequence 23 sequence error message field description specifications 38 header specifications 23 record type specifications 27 sequencing on field description specifications 38 on header specifications 23 on record type specifications 27 using control fields 42 sequence specifications for a summary tag along sort (SORTRS) 21 for a tag along sort (SORTR) 19 for an addrout sort (SORTA) 20 how number of affects sort time 111 how to enter during BUILD cycle 98 how to enter during CALL cycle 99 how to enter during LOAD cycle 94 how to enter when in KSE-created source library entry 94 how to supply 103 inserting new ones in field description lines 38 inserting new ones in record type lines 27

sequence specifications (continued) interrelationship with conversational OCL 101 maximum number 86 normal order 8 recommended number for sort job 111 using additional to decrease sort time 111 ways to supply for Model 6 101 sequence specification sheet location and purpose of specification types 7 types of specifications 7 set include set 28 mixing include and omit sets 29 omit set 29 rules for using include and omit sets 28 types of include sets 28 types of omit sets 29 seven-track tape considerations 15 severe error message (S) 121 sign code packed and unpacked numeric data 32 placement in packed and unpacked numeric data 33 signed numbers how to code when used as factor 2 (columns 20-39-record type specifications) 35 possible sign codes 32 size of main storage, effect on sort time 110 sizes of records, effect on sort time 110 sort jobs examples of addrout and tag along sorts 55 examples of summary sorts 67 information you must supply with OCL 9 types 5 sort time affected by location of files 111 affected by main storage size 110 affected by number of records 110 affected by number of sequence specifications 111 affected by order of control fields 113 affected by record size 110 affected by using alternate collating sequence 111 affected by using automatic work file allocation 113 SORTA (addrout sort) contents of sorted records 5 example 58 sequence specifications 20 using summary data fields 40 sorted file, contents 6 SORTR (tag along sort) calculating output record length when dropping control fields 23 calculating output record length when not dropping control fields 23 contents of sorted records 5 function 5 sequence specifications 19 using summary data fields 40 SORTRS (summary sort) contents of sorted records 6 examples 67 sequence specifications 21 using overflow indicator fields 52 using summary data fields 40

standard collating sequence specified on header line (column 26) 23 table 106 when digit portion is used 107 when zone and digit portions are used 107 when zone portion is used 107 storage, main amount used by sequence specifications 111 how size affects sort time 110 summary data fields how overflow indicated 52 how to define 40 maximum number defined 40 used by each type of sort 40 summary overflow field how to define 46 how to initialize 52 summary sort (SORTRS) (see SORTRS) summary sort overflow 52 summary tag along sort (see SORTRS) supplying sequence specifications for Model 6 advantages and disadvantages of methods 100 System/3 data alphameric 31 how characters represented with the computer 31 how signed numeric constants represent on record type specifications 35 how to interpret 31 in compare operations 30 numeric data 31 zone and digit portion of characters 31

tag along and addrout sorts, comparison 14 tag along sort (SORTR) (see SORTR) temporary file, additional OCL statements needed 9 terminal message (T) 110 time to sort a file addrout and tag along sort comparison 14 affected by alternate collating sequence 111 affected by file location on disk 111 affected by main storage assigned to disk sort 110 affected by number of input records 110 affected by number of sequence specifications 111 affected by order of control fields 113 affected by size of records 110 timing factors affecting sort time 17 samples 114 to entry (columns 13-16-field description specifications) describing one character field 45 to indicate last position of field in input record 44 to entry (columns 24-27-record type), to identify last

position of factor 1 in input record 35 translation table and alternate collating sequence sheet 109 unconditional force example 47 explanation 39 unconditional force character, how to define 46 unpacked numeric data number of bits in each digit 32 position of the sign code 33 possible positive and negative sign codes 32 using duplicate control fields 40

warning message (W) 110 work file calculating storage tracks for 116 considerations 13 considering size when programming 18 defined during BUILD cycle 96 defined during LOAD cycle 93 how position on disk affects sort time 111 OCL statements needed to describe if temporary 9 work record length affected by type of output 116 affected by type of sort 116 work record, how used by disk sort 4

zone, portion of System/3 character 31

7-track tape considerations 15 9-track tape considerations 16

Ξ 

### **International Business Machines Corporation**

General Systems Division 4111 Northside Parkway N.W. P.O. Box 2150 Atlanta, Georgia 30301 (U.S.A. only)

General Business Group/International 44 South Broadway White Plains, New York 10601 U.S.A. (International)