BLISS-36 CompilerInstallation Notes

Order No. AA-J937E-TK

November 1984

This document describes the process by which a BLISS-36 compiler is installed on a TOPS-10 or TOPS-20 system. It should be read before the installation is attempted.

OPERATING SYSTEM AND VERSION: TOPS-10 V7.01A, TOPS-20

V5.1(KL), TOPS-20 V4.1(KS)

SOFTWARE VERSION: BLISS-36 V4A(225) implementing

BLISS language V4.1

First Printing, May 1980
Revised, December 1980
Revised, November 1981
Revised, March 1982
Revised, September 1983
Revised, February 1984
Revised, November 1984

The information in this document is subject to change without notice and should not be construed as a commitment by Digital Equipment Corporation. Digital Equipment Corporation assumes no responsibility for any errors that may appear in this document.

The software described in this document is furnished under a license and may be used or copied only in accordance with the terms of such license.

No responsibility is assumed for the use or reliability of software on equipment that is not supplied by Digital Equipment Corporation or its affiliated companies.

Copyright (c) 1980, 1981, 1982, 1983, 1984 by Digital Equipment Corporation All Rights Reserved.

Printed in U.S.A.

The postpaid READER'S COMMENTS form on the last page of this document requests the user's critical evaluation to assist in preparing future documentation.

The following are trademarks of Digital Equipment Corporation:

DIBOL RSTS DEC EduSystem DEC/CMS RSX DEC/MMS UNIBUS IAS DECnet MASSBUS VAX DECsystem-10 MICRO/PDP-11 VMS Micro/RSX VT DECSYSTEM-20 **DECUS** PDP digital PDT DECwriter

ZK2728

HOW TO ORDER ADDITIONAL DOCUMENTATION

In Continental USA and Puerto Rico call 800-258-1710

In New Hampshire, Alaska, and Hawaii cail 603-884-6660

In Canada call 613-234-7726 (Ottawa-Hull) 800-267-6146 (all other Canadian)

DIRECT MAIL ORDERS (USA & PUERTO RICO)*

Digital Equipment Corporation P.O. Box CS2008 Nashua, New Hampshire 03061

*Any prepaid order from Puerto Rico must be placed with the local Digital subsidiary (809-754-7575)

DIRECT MAIL ORDERS (CANADA)

Digital Equipment of Canada Ltd. 940 Belfast Road Ottawa, Ontario K1G 4C2 Attn: P&SG Business Manager

DIRECT MAIL ORDERS (INTERNATIONAL)

Digital Equipment Corporation P&SG Business Manager c/o Digital's local subsidiary or approved distributor

Internal orders should be placed through the Software Distribution Center (SDC), Digital Equipment Corporation, Northboro, Massachusetts 01532

CONTENTS

			Page
CHAPTER	1	INTRODUCTION PLEASE READ	
CHAPTER	2	INSTALLATION PROCEDURES FOR TOPS-20	
	2.1 2.2 2.3 2.4 2.5 2.6 2.7	NORMAL INSTALLATION PROCEDURES	2-3 2-4 2-5
CHAPTER	3.1 3.2 3.3 3.4 3.5	INSTALLATION PROCEDURES FOR TOPS-10 NORMAL INSTALLATION PROCEDURES	
	3.6 3.7	INSTALLATION DIRECTORY	. 3-5 . 3-6 . 3-7

CHAPTER 1

INTRODUCTION -- PLEASE READ

This document is designed to help you install BLISS-36 Version 4.1 on either a TOPS-10 or TOPS-20 system. During normal installation, you will copy the release tape to disk and submit the installation batch control file INS36.CTL, setting the time limit at 30 minutes. This procedure installs BLISS-36 using devices SYS:, BLI:, DOC:, and HLP:. It is assumed that these devices are available and may be written to, and that the latest version of LINK (LINK-10 V4A, LINK-20 V5.1 (KL), LINK-20 V4.1 (KS)) is available on your system area. Refer to the installation batch control file (INS36.CTL) and the appropriate chapter listed in the table of contents if you have any difficulties with the installation or if you wish to perform a nonstandard installation.

CHAPTER 2

INSTALLATION PROCEDURES FOR TOPS-20

2.1 NORMAL INSTALLATION PROCEDURES

This section describes installation procedures that you can use when performing a normal BLISS-36 installation. A later section describes variations you may use.

1. Log in to an account that allows you write and delete access to the devices SYS:, BLI:, DOC:, and HLP:. Connect to a directory that has at least 2600 free pages of working storage. Installation is easier if the directory is empty when you begin. For this sample installation, the directory is called <USER-DEFINED-AREA> on device DSKX. To connect, type the following at the "@" prompt:

CONNECT DSKX: <USER-DEFINED-AREA>

2. Transfer the release kit files from the tape to the directory. The tape has four save sets. The first save set contains the documentation files, and the second save set contains the remaining files needed for the installation procedure. The third and fourth save sets are duplicate save sets provided in case the files are garbled. You must make sure that the proper tape parameters are used. Type the following:

SET TAPE DENSITY 1600 SET TAPE RECORD-LENGTH 512

3. Mount the tape by typing the following:

MOUNT TAPE BLSTP: /LABEL:UNLABELED/READ-ONLY

4. Run DUMPER to transfer the contents of the tape to the disk area:

@DUMPER
DUMPER>TAPE BLSTP:
DUMPER>SUPERSEDE ALWAYS
DUMPER>REWIND
DUMPER>ACCOUNT SYSTEM-DEFAULT
DUMPER>FILES
DUMPER>RESTORE PS:<*>*.*.* DSKX:<USER-DEFINED-AREA>*.*.-1
DUMPER>RESTORE PS:<*>*.*.* DSKX:<USER-DEFINED-AREA>*.*.-1

"DUMPER>" is the DUMPER program's prompt. You should substitute your own device and directory in the RESTORE command. This should cause the files to be transferred from the tape to the specified area. Each file name will be displayed on your terminal as it is transferred.

Do not type anything while the files are being transferred. Type the following once you receive the DUMPER> prompt:

EXIT

This will return you to the "@" prompt. It is recommended that you keep your tape mounted until the BLISS system is completely installed. If you need the drive, however, dismount the tape by typing the following at the "@" prompt:

DISMOUNT BLSTP:

5. Now you are ready to install BLISS-36. A BATCH command file has been provided to do the work for you. If the account you are logged in to requires that capabilities be enabled before it can write-access the areas on which the BLISS-36 system will be installed, add an "ENABLE" command to the BLISS.CMD file. Run the installation batch control file on a KL processor by typing the following at the "@" prompt:

SUBMIT INS36.CTL/TIME:00:30:00

To run the installation batch control file on a KS processor, type:

SUBMIT INSKS.CTL/TIME:02:30:00

You should receive another prompt almost immediately.

Wait for the batch job to complete. You can check to see if it is still running by typing:

INFORMATION BATCH

On most systems this can be abbreviated to:

ΙB

When INS36 no longer appears in the batch queue listing, examine the resulting log file. The file will be called "INS36.LOG." On most systems the above SUBMIT causes the log file to spool automatically to the line printer.

Look first at the last few lines of the log file. If a message such as the following appears, something has gone wrong with the installation procedure:

****	******	*****	*****	*****	*****	*****	****
*							*
*		INSTALLAT	ON OF	F BLISS-36	FAILED		*
*							*
****	******	*****	****	******	*****	*****	*****

Read Section 2.2 to find out why the installation failed and how to correct the problem. If the installation is successful, you will see the message:

******	*****	******	****	*****	******
*					*
*	SUCCESSFUL	INSTALLATION	OF E	BLISS-36	*
*					*
********	******	***********	****	******	. * * * * * * * * * * * * *

If the installation is successful, skip to Section 2.4 entitled "After Installation."

2.2 WHAT TO DO IF SOMETHING GOES WRONG

If you closely follow the procedures in this document, you should not encounter any serious installation problems.

If you run out of space during installation, we suggest that you delete and expunge any previous versions of the files being transferred.

If files on the tape are garbled, duplicate save sets are provided on the tape. To get to them, follow the directions for mounting and initializing DUMPER. On the line following DUMPER>FILES, however, type:

SKIP 2

This will move you to the start of the duplicate save sets. Now use the RESTORE command to dump either the entire set of files or individual files that were garbled on the first save set.

If the INS36 batch job failed to complete, search the listing until you find the last statement that was executed. This last statement will be followed by an error message, which starts with a question mark. Comments have been inserted in the file to provide you with some idea of what went wrong. If you need further help, contact your system manager.

There are three types of corrective action you can take if the INS36 batch job failed to complete:

- You can replace a file, possibly from the duplicate save sets as previously described.
- 2. You can modify INS36.CTL. Comments have been provided to assist you.
- 3. You can modify the release files, though generally this should not be done since you are likely to create more problems than you solve.

You should delete the previous copy of INS36.LOG before running the batch job again. If you do not, the files will be concatenated by the batch spooler. Some installations include a /BATCH-LOG:SUPERSEDE switch on a SUBMIT that causes the previous log file, if any, to be superseded rather than concatenated. If such a switch is available, you should use it.

2.3 VARIATIONS IN INSTALLATION PROCEDURES

No one installation procedure can accommodate all systems. You can tailor the procedure to your system by editing INS36.CTL and reading the comments in that file.

The most common variation in this procedure is installing BLISS-36 on a nonstandard device. With many systems, you must first install new software in a temporary area until all concerned are satisfied with its reliability. Because we try very hard to guarantee that every release is as reliable as any previous release, you are encouraged to install BLISS-36 directly on SYS:. However, if you still wish to install BLISS-36 in a temporary area, read on.

There are three ways you can redirect the installation procedure to another device. The simplest way is to use the file BLISS.CMD. The INS36.CTL will look for BLISS.CMD and execute the commands from this

file. You can add to this file some alternate definitions for devices SYS:, BLI:, DOC:, and HLP:. For example, the following will cause any files written to device SYS: to go to device NEW:; an attempt to read a file from SYS: will find the file on SYS: if it is not on NEW::

DEFINE SYS: NEW:, SYS:

Another way to redirect the installation procedure is to change the definitions appearing in INS36.CTL. These definitions allow you more control over what goes where. Comments appearing with the device definitions explain what each logical device name means.

The third method to redirect the installation procedure is to find the place in INS36.CTL where the files in question are transferred and modify that line appropriately. This allows you the most control over the redirection but requires the most work.

A link-time constant has been added to enable the compiler to generate indirect-through-memory instructions. This capability is disabled by default.

To change the default, modify BLISS.LNK where it defines the link-time constant INDIR. The link commands have the following meaning:

/DEFINE:INDIR:0 - No indirect-through-memory instructions /DEFINE:INDIR:1 - Indirect-through-memory instructions

2.4 AFTER INSTALLATION

A few cleanup tasks remain once installation is complete.

Most importantly, place a note in the system login messages to inform users that BLISS-36 has been installed. Because the procedures for doing this vary widely from system to system, the note is not included in the installation batch file. The file "BLISS.NTC," supplied with the kit, contains a typical message which you can modify.

It is recommended that the installation area, to which you dumped the tape, be kept intact. This will make updates and modifications much easier. If, however, disk space is at a premium on your system, you can delete these files in either of two ways:

1. If the area was empty when you started, type the following at the "0" prompt:

DELETE *.*, @EXPUNGE

2. If there were files that you wish to keep on the disk, typing the following will delete most of the files:

SUBMIT DEL36.CTL/TIME:00:30:00

When this is done, you may type the following to delete the rest of the files:

DELETE DEL36.*, @EXPUNGE

2.5 DIRECTORY OF TAPE

The following is a list of the files included on the first save set of the installation tape:

BCREF.HLP
BLISS.BWR
BLISS.DOC
BLISS.HLP
BLISS.INS
CVT10.DOC
CVT10.HLP
DEL36.CTL
DMPREL.HLP
INS36.CTL
INSKS.CTL
MONINT.DOC
SIX12.HLP
SIX12.MEM
TUTIO.HLP

B361AB.REL

The following is a list of the files included on the second save set of the installation tape:

B361AT.REL B361LB.REL B361LT.REL B362LB.REL B362PB.REL BCREF.EXE BLISS.CMD BLISS.LNK BLISS.NTC BLISS.REL BLSOTS.MAC CHKC2L.B36 CHKEXT.B36 CHKMKL.EXE CHKMT2.EXE CVT10.EXE CVT10.SNO DEB36.LNK DEB36.REL DMPREL.EXE ERROR.BNR EZIO10.B36 EZIO10.REL EZIO20.B36 EZIO20.REL FLDDB.R36 LSTCHK.BLI MONINT.EXE MONSYM.L36 MONSYM.R36 NORMAL.BNR PSI20.B36 REG1AB.MAC REGIAT.MAC REG1LB.MAC REGILT.MAC REG2LB.MAC REG2PB.MAC SIX12.B36 TENDEF.L36

TENDEF.R36

TUTIO.R36 UUOSYM.R36 UUOSYM.R36 XDUMP.REL XPORT.L36 XPORT.REQ XPOT10.DBG XPOT10.REL XPOT20.DBG XPOT20.REL

2.6 INSTALLATION DIRECTORY

The following is a list of the files that this installation procedure actually installs. The device name given is the default device to which the file is transferred. The files that go to device NUL: are not installed by default.

SYS:B361AB.REL SYS:B361AT.REL SYS:B361LB.REL SYS:B361LT.REL SYS:B362LB.REL SYS:B362PB.REL SYS:BCREF.EXE HLP: BCREF. HLP DOC:BLISS.BWR DOC:BLISS.DOC SYS:BLISS.EXE HLP:BLISS.HLP NUL:BLISS.REL BLI:BLSOTS.MAC DOC:CVT10.DOC SYS:CVT10.EXE HLP:CVT10.HLP BLI:CVT10.SNO SYS: DEB 36. EXE NUL:DEB36.REL SYS:DMPREL.EXE HLP:DMPREL.HLP BLI:EZIO10.B36 BLI: EZIO10. REL BLI:EZIO20.B36 BLI:EZIO20.REL BLI:FLDDB.R36 DOC: MONINT. DOC SYS:MONINT.EXE BLI:MONSYM.L36 BLI:MONSYM.R36 BLI:REG1AB.MAC BLI:REG1AT.MAC BLI:REG1LB.MAC BLI:REGILT.MAC BLI:REG2LB.MAC BLI: REG2PB.MAC BLI:SIX12.B36 HLP:SIX12.HLP DOC:SIX12.MEM BLI:TENDEF.L36 BLI: TENDEF. R36 HLP:TUTIO.HLP BLI:TUTIO.R36 BLI:UUOSYM.L36 BLI: UUOSYM.R36

SYS:XDUMP.EXE BLI:XDUMP.REL BLI:XPORT.DBG BLI:XPORT.L36 BLI:XPORT.REL BLI:XPORT.REQ BLI:XPOT10.DBG BLI:XPOT10.REL BLI:XPOT20.DBG BLI:XPOT20.DBG

2.7 IMPORTANT FILES

The following are important files in the installation kit that you should be familiar with. These files may be in one or both of the two previous directories.

- B36*.REL -- various versions of the BLISS run-time system
- BCREF.EXE -- the BLISS cross-reference postprocessor
- BCREF.HLP -- a help file for using BCREF.EXE
- BLISS.BWR -- the restriction section from BLISS.DOC
- BLISS.DOC -- a brief description of BLISS-36 V4.1 for users and potential users of BLISS
- BLISS.EXE -- the BLISS-36 compiler itself
- BLISS.HLP -- a help file on how to run BLISS
- BLISS.NTC -- a sample login message informing users that BLISS-36 has been installed
- DEL36.CTL -- a file that cleans out the installation area
- INS36.CTL -- a file that installs the BLISS-36 system from the installation area
- INSKS.CTL -- version of INS36.CTL for use on a KS processor
- BLISS.INS -- this document
- XPOT10.DBG -- special TOPS-10 XPORT debug object file for use with the SIX12 debugger
- XPOT10.REL -- standard TOPS-10 XPORT object file
- XPOT20.DBG -- special TOPS-20 XPORT debug object file for use with the SIX12 debugger
- XPOT20.REL -- standard TOPS-20 XPORT object file

CHAPTER 3

INSTALLATION PROCEDURES FOR TOPS-10

3.1 NORMAL INSTALLATION PROCEDURES

This section describes installation procedures that you can use in performing a normal BLISS-36 installation. A later section describes variations you may use.

- 1. Log in to an account that allows you write and delete access to the devices SYS:, BLI:, DOC:, and HLP:. Connect to a directory that has at least 8000 blocks of free storage. Installation is easier if the directory is empty when you begin.
- 2. Transfer the release kit files from the tape to the directory. The tape has four save sets. The first save set contains the documentation files, and the second save set contains the remaining files needed for the installation procedure. The third and fourth save sets are duplicate save sets provided in case the files are garbled.
- 3. Mount the tape. There may be some variation between systems but the following applies to most systems. At the "." prompt, type:

MOUNT MTA: BTP: /RONLY /REELID:BLISS

Set the tape parameters:

SET BLOCKSIZE BTP: 512

Check the label printed on the tape and depending on which density it specifies, type either:

SET DENSITY BTP: 800

or

SET DENSITY BTP: 1600

4. Now run BACKUP:

```
.R BACKUP
/TAPE BTP:
/REWIND
/INTERCHANGE
/SUPERSEDE ALWAYS
/FILES
/RESTORE DSK:*.*[-] = ALL:*.*[*,*]
/RESTORE DSK:*.*[-] = ALL:*.*[*,*]
```

The "/" is a prompt supplied by BACKUP. The files should be transferred from the tape to the specified area. Each file name will be displayed on your terminal as it is transferred.

Do not type anything while the files are being transferred. Once you receive a prompt, type:

```
/REWIND
/CHECK DSK:*.*[-]
/CHECK DSK:*.*[-]
```

The program will check each file on the disk against the file on the tape. As each file is checked, its name will be displayed on your terminal. An error message will be displayed if the files are not identical.

Wait for this process to complete, then type the following at the "/" prompt:

EXIT

This should return you to the monitor.

It is recommended that you keep your tape mounted until BLISS-36 is completely installed. However, if you need the drive, dismount the tape by typing the following at the "." prompt:

DISMOUNT BTP:

5. Now you are ready to install BLISS-36. A BATCH command file has been provided to do the work for you. On some (nonstandard) systems, accounting information must be included at the beginning of BATCH files. If this is the case on your system, edit that information into INS36.CTL. To run the installation batch control file, type the following at the "." prompt:

SUBMIT INS36.CTL/TIME:00:10:00

You will receive another prompt from the monitor almost immediately.

Wait for the batch job to complete. You can check to see if it is still running by typing the following at the "." prompt:

SUBMIT

When INS36 no longer appears in the batch queue listing, examine the resulting log file. The file will be called "INS36.LOG." On most systems the previously mentioned SUBMIT command will cause the log file to spool automatically to the line printer.

Look first at the last few lines of the log file. If the following message appears, something has gone wrong with the installation procedure:

Read Section 3.2 to find out why the installation failed and how to correct the problem. If the installation is successful, you will see the message:

If the installation is successful, skip to Section 3.4 entitled "After Installation."

3.2 WHAT TO DO IF SOMETHING GOES WRONG

If you closely follow the procedures in this document, you should not encounter any serious installation problems.

If you run out of space at any point, we suggest that you delete any previous versions of the files being transferred.

If files on the tape are garbled, duplicate save sets are provided on the tape. To get to them, follow the directions in Section 3.1 for mounting and initializing BACKUP. Following the line /FILES, however, type the following at the "/" prompt:

SKIP 2

This will move you to the start of the duplicate save sets. Now use the RESTORE command to dump either the entire set of files or individual files that were garbled on the first save set.

If the INS36 batch job failed to complete, search the listing until you find the last statement that executed. This last statement will be followed by an error message, which starts with a question mark. Comments have been inserted in the file to provide you with some idea of what went wrong. If you need further help, contact your system manager.

There are three types of corrective action you can take if the INS36 batch job failed to complete:

- You can replace a file, possibly from the duplicate save sets previously described.
- You can modify INS36.CTL. Comments have been provided to assist you.
- You can modify the release files, though generally this should not be done since you are likely to create more problems than you solve.

You should delete the previous copy of INS36.LOG before running the batch job again. If you do not, the files will be concatenated by the batch spooler.

3.3 VARIATIONS IN INSTALLATION PROCEDURES

No one installation procedure can accommodate all systems. You can tailor the procedure to your system by editing INS36.CTL and reading the comments in that file.

The most common variation in this procedure is installing BLISS-36 on a nonstandard device. With many systems, you must first install new software in a temporary area until all concerned are satisfied with its reliability. Because we try very hard to guarantee that every release is as reliable as any previous release, you are encouraged to install BLISS-36 directly on SYS:. However, if you still wish to install BLISS-36 in a temporary area, read on.

There are three ways you can redirect the installation procedure to another device. One way is to change the definitions in INS36.CTL. Comments appearing with the device definitions explain what each logical device name means.

A second way involves finding the place in INS36.CTL where the file(s) in question are transferred and modifying that line as desired. This procedure allows a finer control but requires considerably more work.

A link-time constant has been added that enables the compiler to generate indirect-through-memory instructions. The default disables this capability.

To change the default, modify SEGCMN.LNK where it defines the link-time constant INDIR. The link commands have the following meaning:

```
/DEFINE:INDIR:0 - No indirect-through-memory instructions /DEFINE:INDIR:1 - Indirect-through-memory instructions
```

A link-time constant has been added to specify the default processor model of the target system for which code is to be generated. The default is currently set to KL10/KS10.

To change the default, modify SEGCMN.LNK where it defines the link-time constant CPUTYP. The link commands have the following meaning:

```
/DEFINE:CPUTYP:0 - Target system is a KA10
/DEFINE:CPUTYP:1 - Target system is a KI10
/DEFINE:CPUTYP:2 - Target system is a KL10 or KS10
```

3.4 AFTER INSTALLATION

A few cleanup tasks remain once installation is complete.

Most importantly, place a note in the system login messages notifying users that BLISS-36 has been installed. Because the procedures for doing this vary widely from system to system, the note is not included in the installation batch file. The file "BLISS.NTC," supplied with the kit, contains a typical message which you can modify.

It is recommended that the installation area, to which you dumped the tape, be kept intact. This will make updates and modifications easier. If, however, disk space is at a premium on your system, you can delete these files in either of two ways:

1. If the area was empty when you started, type the following at the "." prompt:

DELETE *.*

2. If there were files that you wish to keep on the area, typing the following at the "." prompt will delete most of the files:

SUBMIT DEL36.CTL/TIME:00:10:00

When this is done, you may type the following to delete the rest the rest of the files:

.DELETE DEL36.*

3.5 DIRECTORY OF TAPE

The following is a list of the files included on the first save set of the installation tape:

BCREF.HLP BLISS.BWR BLISS.DOC BLISS.HLP BLISS.INS CVT10.DOC CVT10.HLP DEL36.CTL DMPREL.HLP INS36.CTL MONINT.DOC SIX12.HLP SIX12.MEM TUTIO.HLP

The following is a list of the files included on the second save set of the installation tape:

B361AB.REL B361AT.REL B361LB.REL B361LT.REL BCREF.EXE BLISS.NTC BLISS.REL BLSOTS.MAC CVT10.EXE CVT10.SNO DEB36.LNK DEB36.REL DMPREL.EXE ERROR.BNR EZIO10.B36 EZIO10.REL LSTCHK.BLI MONINT.EXE NORMAL.BNR REG1AB.MAC REGIAT.MAC REG1LB.MAC REG1LT.MAC SEG1.LNK SEG2.LNK SEG3.LNK SEG4.LNK SEG5.LNK SEGCMN.LNK SIX12.B36 TENDEF.L36 TENDEF.R36 TUTIO.R36

UUOSYM.L36

UUOSYM.R36 XDUMP.REL XPORT.L36 XPORT.REQ XPOT10.DBG XPOT10.REL

3.6 INSTALLATION DIRECTORY

The following is a list of the files that this installation procedure actually installs. The device name given is the default device to which the file is transferred. Those files going to device DSK: are not installed by default.

SYS:B361AB.REL SYS:B361AT.REL SYS:B361LB.REL SYS:B361LT.REL SYS: BCREF. EXE HLP:BCREF.HLP DOC:BLISS.BWR DOC:BLISS.DOC HLP:BLISS.HLP DSK:BLISS.REL SYS:BLISS.EXE BLI:BLSOTS.MAC SYS:BLSSG2.EXE SYS:BLSSG3.EXE SYS: BLSSG4. EXE SYS:BLSSG5.EXE DOC:CVT10.DOC SYS:CVT10.EXE HLP:CVT10.HLP BLI:CVT10.SNO SYS: DEB 36. EXE DSK: DEB36.REL SYS: DMPREL. EXE HLP: DMPREL. HLP BLI:EZIO10.B36 BLI: EZIO10.REL DOC: MONINT. DOC SYS:MONINT.EXE BLI: REG1AB. MAC BLI: REGIAT. MAC BLI:REG1LB.MAC BLI:REG1LT.MAC BLI:SIX12.B36 HLP:SIX12.HLP DOC:SIX12.MEM BLI:TENDEF.L36 BLI: TENDEF. R36 HLP:TUTIO.HLP BLI:TUTIO.R36 BLI:UUOSYM.L36 BLI: UUOSYM.R36 SYS: XDUMP. EXE BLI:XDUMP.REL BLI:XPORT.DBG BLI:XPORT.L36 BLI:XPORT.REL BLI: XPORT. REQ BLI:XPOT10.DBG BLI:XPOT10.REL

3.7 IMPORTANT FILES

The following are some important files in the installation kit that you should be familiar with. These files may be found in one or both of the two previous sections.

- B36*.REL -- various versions of the BLISS run-time system
- BCREF.EXE -- the BLISS cross-reference postprocessor
- BCREF.HLP -- a help file for using BCREF.EXE
- BLISS.BWR -- the restriction section from BLISS.DOC
- BLISS.DOC -- a brief description of BLISS-36 V4.1 for users and potential users of BLISS
- BLISS.HLP -- a help file on how to run BLISS
- BLISS.NTC -- a sample login message informing users that BLISS-36 has been installed
- BLISS.EXE -- the BLISS-36 compiler low-segment and high-segment overlay 1
- BLSSG2.EXE -- the BLISS-36 compiler high-segment overlay 2
- BLSSG3.EXE -- the BLISS-36 compiler high-segment overlay 3
- BLSSG4.EXE -- the BLISS-36 compiler high-segment overlay 4
- BLSSG5.EXE -- the BLISS-36 compiler high-segment overlay 5
- DEL36.CTL -- a file that cleans out the installation area
- INS36.CTL -- a file that installs the BLISS-36 system from the installation area
- BLISS.INS -- this document
- XPOT10.DBG -- special TOPS-10 XPORT debug object file for use with the SIX12 debugger
- XPOT10.REL -- standard TOPS-10 XPORT object file

READER'S COMMENTS

NOTE: This form is for document comments only. DIGITAL will use comments submitted on this form at the company's discretion. If you require a written reply and are eligible to receive one under Software Performance Report (SPR) service, submit your comments on an SPR form.

Did you find this manual u	nderstandable, usable, and w	vell organized? Please mak	e suggestions for improvement.
- M			
	WITH STATE OF THE		
Did you find errors in this	manual? If so, specify the err	or and the page number.	
Please indicate the type of	user/reader that you most nea	arly represent.	
	lage programmer		
	nguage programmer grammer (experienced)		
	programming experience		
Student progra	mmer		
Other (please s	pecify)		
Name		Date	
Organization			
City		State	Zip Code or Country



No Postage Necessary if Mailed in the United States

1

BUSINESS REPLY MAIL

FIRST CLASS PERMIT NO.33 MAYNARD MASS.

POSTAGE WILLBE PAID BY ADDRESSEE

SSG PUBLICATIONS ZK1-3/J35 DIGITAL EQUIPMENT CORPORATION 110 SPIT BROOK ROAD NASHUA, NEW HAMPSHIRE 03062-2698